

SDTS_AL

Contents

1 ISO8211Lib	1
2 sdts_al_main	5
3 SDTS_AL_TUT	9
4 sdts2shp.cpp	17
5 ISO8211_Example	29
6 Class Index	33
6.1 Class Hierarchy	33
7 Class Index	37
7.1 Class List	37
8 File Index	41
8.1 File List	41
9 Class Documentation	43
9.1 _CPLHashSet Struct Reference	43
9.2 _CPLList Struct Reference	43
9.2.1 Detailed Description	43
9.2.2 Member Data Documentation	43
9.2.2.1 pData	43
9.2.2.2 psNext	43
9.3 _CPLQuadTree Struct Reference	44
9.4 _QuadTreeNode Struct Reference	44
9.5 CPLErrorContext Struct Reference	44
9.6 CPLHTTPResult Struct Reference	44
9.6.1 Detailed Description	44
9.6.2 Member Data Documentation	44
9.6.2.1 nDataLen	44
9.6.2.2 nMimePartCount	44

9.6.2.3	nStatus	45
9.6.2.4	pabyData	45
9.6.2.5	papszHeaders	45
9.6.2.6	pasMimePart	45
9.6.2.7	pszContentType	45
9.6.2.8	pszErrBuf	45
9.7	CPLKeywordParser Class Reference	45
9.8	CPLMimePart Struct Reference	45
9.8.1	Detailed Description	45
9.8.2	Member Data Documentation	46
9.8.2.1	nDataLen	46
9.8.2.2	pabyData	46
9.8.2.3	papszHeaders	46
9.9	CPLODBCDriverInstaller Class Reference	46
9.9.1	Detailed Description	46
9.9.2	Member Function Documentation	46
9.9.2.1	InstallDriver	46
9.9.2.2	RemoveDriver	47
9.10	CPLODBCSession Class Reference	47
9.10.1	Detailed Description	47
9.10.2	Member Function Documentation	47
9.10.2.1	EstablishSession	47
9.10.2.2	GetLastError	48
9.11	CPLODBCStatement Class Reference	48
9.11.1	Detailed Description	49
9.11.2	Member Function Documentation	49
9.11.2.1	Append	49
9.11.2.2	Append	49
9.11.2.3	Append	49
9.11.2.4	AppendEscaped	49
9.11.2.5	Appendf	49
9.11.2.6	Clear	50
9.11.2.7	DumpResult	50
9.11.2.8	ExecuteSQL	50
9.11.2.9	Fetch	50
9.11.2.10	GetColCount	51
9.11.2.11	GetColData	51
9.11.2.12	GetColData	51
9.11.2.13	GetColId	51
9.11.2.14	GetColName	52

9.11.2.15 GetColNullable	52
9.11.2.16 GetColPrecision	52
9.11.2.17 GetColSize	52
9.11.2.18 GetColType	53
9.11.2.19 GetColTypeName	53
9.11.2.20 GetColumns	53
9.11.2.21 GetPrimaryKeys	54
9.11.2.22 GetTables	54
9.11.2.23 GetTypeMapping	54
9.11.2.24 GetTypeName	54
9.12 CPLRectObj Struct Reference	55
9.13 CPLSharedFileInfo Struct Reference	55
9.14 CPLStdCallThreadInfo Struct Reference	55
9.15 CPLXMLNode Struct Reference	55
9.15.1 Detailed Description	56
9.15.2 Member Data Documentation	56
9.15.2.1 eType	56
9.15.2.2 psChild	56
9.15.2.3 psNext	56
9.15.2.4 pszValue	56
9.16 ctb Struct Reference	56
9.17 curfile_info Struct Reference	57
9.18 DDFField Class Reference	57
9.18.1 Detailed Description	57
9.18.2 Member Function Documentation	57
9.18.2.1 Dump	57
9.18.2.2 GetData	57
9.18.2.3 GetDataSize	57
9.18.2.4 GetFieldDefn	58
9.18.2.5 GetInstanceData	58
9.18.2.6 GetRepeatCount	58
9.18.2.7 GetSubfieldData	58
9.19 DDFFieldDefn Class Reference	59
9.19.1 Detailed Description	59
9.19.2 Member Function Documentation	59
9.19.2.1 Dump	59
9.19.2.2 FindSubfieldDefn	59
9.19.2.3 GetDefaultValue	60
9.19.2.4 GetDescription	60
9.19.2.5 GetFixedWidth	60

9.19.2.6 GetName	60
9.19.2.7 GetSubfield	60
9.19.2.8 GetSubfieldCount	60
9.19.2.9 IsRepeating	60
9.19.2.10 SetRepeatingFlag	61
9.20 DDFModule Class Reference	61
9.20.1 Detailed Description	61
9.20.2 Constructor & Destructor Documentation	61
9.20.2.1 DDFModule	61
9.20.2.2 ~DDFModule	61
9.20.3 Member Function Documentation	62
9.20.3.1 AddField	62
9.20.3.2 Close	62
9.20.3.3 Dump	62
9.20.3.4 FindFieldDefn	62
9.20.3.5 GetField	62
9.20.3.6 GetFieldCount	63
9.20.3.7 Open	63
9.20.3.8 ReadRecord	63
9.20.3.9 Rewind	63
9.21 DDFRecord Class Reference	63
9.21.1 Detailed Description	64
9.21.2 Member Function Documentation	64
9.21.2.1 AddField	64
9.21.2.2 Clone	64
9.21.2.3 CloneOn	65
9.21.2.4 CreateDefaultFieldInstance	65
9.21.2.5 DeleteField	65
9.21.2.6 Dump	66
9.21.2.7 FindField	66
9.21.2.8 GetData	66
9.21.2.9 GetDataSize	66
9.21.2.10 GetField	66
9.21.2.11 GetFieldCount	66
9.21.2.12 GetFloatSubfield	67
9.21.2.13 GetIntSubfield	67
9.21.2.14 GetModule	67
9.21.2.15 GetStringSubfield	67
9.21.2.16 ResizeField	68
9.21.2.17 SetFieldRaw	68

9.21.2.18 SetFloatSubfield	68
9.21.2.19 SetIntSubfield	69
9.21.2.20 SetStringSubfield	69
9.21.2.21 Write	69
9.22 DDFSubfieldDefn Class Reference	70
9.22.1 Detailed Description	70
9.22.2 Member Enumeration Documentation	70
9.22.2.1 DDFBinaryFormat	70
9.22.3 Member Function Documentation	71
9.22.3.1 Dump	71
9.22.3.2 DumpData	71
9.22.3.3 ExtractFloatData	71
9.22.3.4 ExtractIntData	71
9.22.3.5 ExtractStringValue	72
9.22.3.6 FormatFloatValue	72
9.22.3.7 FormatIntValue	73
9.22.3.8 FormatStringValue	73
9.22.3.9 GetDataLength	73
9.22.3.10 GetDefaultValue	73
9.22.3.11 GetFormat	74
9.22.3.12 GetName	74
9.22.3.13 GetType	74
9.22.3.14 GetWidth	74
9.23 DefaultCSVFileNameTLS Struct Reference	74
9.24 errHandler Struct Reference	74
9.25 file_in_zip_read_info_s Struct Reference	74
9.26 FindFileTLS Struct Reference	74
9.27 GZipSnapshot Struct Reference	75
9.28 linkedlist_data_s Struct Reference	75
9.29 linkedlist_datablock_internal_s Struct Reference	75
9.30 ParseContext Struct Reference	75
9.31 SDTS_CATD Class Reference	75
9.31.1 Detailed Description	75
9.31.2 Member Function Documentation	75
9.31.2.1 GetEntryFilePath	75
9.31.2.2 GetEntryType	76
9.31.2.3 GetEntryTypeDesc	76
9.32 SDTS_CATDEntry Class Reference	76
9.33 SDTS_IREF Class Reference	76
9.33.1 Detailed Description	77

9.34 SDTS_XREF Class Reference	77
9.34.1 Detailed Description	77
9.34.2 Member Data Documentation	77
9.34.2.1 nZone	77
9.34.2.2 pszDatum	77
9.34.2.3 pszSystemName	77
9.35 SDTSAtrReader Class Reference	77
9.35.1 Detailed Description	78
9.35.2 Member Function Documentation	78
9.35.2.1 IsSecondary	78
9.36 SDTSAtrRecord Class Reference	78
9.36.1 Detailed Description	78
9.36.2 Member Function Documentation	79
9.36.2.1 Dump	79
9.36.3 Member Data Documentation	79
9.36.3.1 poATTR	79
9.36.3.2 poWholeRecord	79
9.37 SDTSDataset Class Reference	79
9.38 SDTSFeature Class Reference	79
9.38.1 Detailed Description	80
9.38.2 Member Function Documentation	80
9.38.2.1 Dump	80
9.38.3 Member Data Documentation	80
9.38.3.1 nAttributes	80
9.38.3.2 oModId	80
9.38.3.3 paoATID	80
9.39 SDTSIndexedReader Class Reference	80
9.39.1 Detailed Description	81
9.39.2 Member Function Documentation	81
9.39.2.1 ClearIndex	81
9.39.2.2 FillIndex	81
9.39.2.3 GetIndexedFeatureRef	81
9.39.2.4 GetNextFeature	81
9.39.2.5 IsIndexed	82
9.39.2.6 Rewind	82
9.39.2.7 ScanModuleReferences	82
9.40 SDTSLineReader Class Reference	82
9.40.1 Detailed Description	83
9.40.2 Member Function Documentation	83
9.40.2.1 AttachToPolygons	83

9.41 SDTSMoId Class Reference	83
9.41.1 Detailed Description	83
9.41.2 Member Data Documentation	83
9.41.2.1 nRecord	83
9.41.2.2 szModule	83
9.41.2.3 szOBRP	84
9.42 SDTSPointReader Class Reference	84
9.42.1 Detailed Description	84
9.43 SDTSPolygonReader Class Reference	84
9.43.1 Detailed Description	84
9.43.2 Member Function Documentation	85
9.43.2.1 AssembleRings	85
9.44 SDTSRasterBand Class Reference	85
9.45 SDTSRasterReader Class Reference	85
9.45.1 Detailed Description	86
9.45.2 Member Function Documentation	86
9.45.2.1 GetBlock	86
9.45.2.2 GetBlockXSize	86
9.45.2.3 GetBlockYSize	86
9.45.2.4 GetMinMax	86
9.45.2.5 GetRasterType	86
9.45.2.6 GetTransform	87
9.45.2.7 GetXSize	87
9.45.2.8 GetYSize	87
9.46 SDTSRawLine Class Reference	87
9.46.1 Detailed Description	88
9.46.2 Member Function Documentation	88
9.46.2.1 Dump	88
9.46.3 Member Data Documentation	88
9.46.3.1 nVertices	88
9.46.3.2 oEndNode	88
9.46.3.3 oLeftPoly	88
9.46.3.4 oRightPoly	88
9.46.3.5 oStartNode	88
9.46.3.6 padfX	89
9.46.3.7 padfY	89
9.46.3.8 padfZ	89
9.47 SDTSRawPoint Class Reference	89
9.47.1 Detailed Description	89
9.47.2 Member Function Documentation	89

9.47.2.1	Dump	89
9.47.3	Member Data Documentation	90
9.47.3.1	dfX	90
9.47.3.2	dfY	90
9.47.3.3	dfZ	90
9.47.3.4	oAreald	90
9.48	SDTSRawPolygon Class Reference	90
9.48.1	Detailed Description	91
9.48.2	Member Function Documentation	91
9.48.2.1	AssembleRings	91
9.48.2.2	Dump	91
9.48.3	Member Data Documentation	92
9.48.3.1	nRings	92
9.48.3.2	nVertices	92
9.48.3.3	padfX	92
9.48.3.4	padfY	92
9.48.3.5	padfZ	92
9.48.3.6	panRingStart	92
9.49	SDTSTransfer Class Reference	92
9.49.1	Detailed Description	93
9.49.2	Member Function Documentation	93
9.49.2.1	FindLayer	93
9.49.2.2	GetAttr	93
9.49.2.3	GetBounds	93
9.49.2.4	GetCATD	94
9.49.2.5	GetLayerCATDEntry	94
9.49.2.6	GetLayerIndexedReader	94
9.49.2.7	GetLayerRasterReader	94
9.49.2.8	GetLayerType	95
9.49.2.9	GetXREF	95
9.49.2.10	Open	95
9.50	SFRegion Class Reference	96
9.51	StackContext Struct Reference	96
9.52	tm_unz_s Struct Reference	96
9.53	tm_zip_s Struct Reference	96
9.54	unz_file_info_internal_s Struct Reference	96
9.55	unz_file_info_s Struct Reference	96
9.56	unz_file_pos_s Struct Reference	96
9.57	unz_global_info_s Struct Reference	96
9.58	unz_s Struct Reference	97

9.59	VSIArchiveContent Struct Reference	97
9.60	VSIArchiveEntry Struct Reference	97
9.61	VSIArchiveEntryFileOffset Class Reference	97
9.62	VSIArchiveFilesystemHandler Class Reference	97
9.63	VSIArchiveReader Class Reference	98
9.64	VSIBufferedReaderHandle Class Reference	98
9.65	VSICacheChunk Class Reference	98
9.66	VSICachedFile Class Reference	98
9.67	VSIFFileManager Class Reference	99
9.68	VSIFilesystemHandler Class Reference	99
9.69	VSIGZipFilesystemHandler Class Reference	99
9.70	VSIGZipHandle Class Reference	100
9.71	VSIGZipWriteHandle Class Reference	100
9.72	VSIMemFile Class Reference	100
9.73	VSIMemFilesystemHandler Class Reference	100
9.74	VSIMemHandle Class Reference	101
9.75	VSISparseFileFilesystemHandler Class Reference	101
9.76	VSISparseFileHandle Class Reference	101
9.77	VSIStdinFilesystemHandler Class Reference	101
9.78	VSIStdinHandle Class Reference	102
9.79	VSIStdoutFilesystemHandler Class Reference	102
9.80	VSIStdoutHandle Class Reference	102
9.81	VSIStdoutRedirectFilesystemHandler Class Reference	103
9.82	VSIStdoutRedirectHandle Class Reference	103
9.83	VSISubFileFilesystemHandler Class Reference	103
9.84	VSISubFileHandle Class Reference	103
9.85	VSITarEntryFileOffset Class Reference	104
9.86	VSITarFilesystemHandler Class Reference	104
9.87	VSITarReader Class Reference	104
9.88	VSIUnixStdioFilesystemHandler Class Reference	105
9.89	VSIUnixStdioHandle Class Reference	105
9.90	VSIVirtualHandle Class Reference	105
9.91	VSIZipEntryFileOffset Class Reference	106
9.92	VSIZipFilesystemHandler Class Reference	106
9.93	VSIZipReader Class Reference	107
9.94	VSIZipWriteHandle Class Reference	107
9.95	zip_fileinfo Struct Reference	107
9.96	zip_internal Struct Reference	108
9.97	zlib_filefunc_def_s Struct Reference	108

10 File Documentation	109
10.1 <code>cpl_conv.h</code> File Reference	109
10.1.1 Detailed Description	110
10.1.2 Function Documentation	110
10.1.2.1 <code>CPLAtof</code>	110
10.1.2.2 <code>CPLAtofDelim</code>	111
10.1.2.3 <code>CPLAtofM</code>	111
10.1.2.4 <code>CPLAlloc</code>	112
10.1.2.5 <code>CPLCheckForFile</code>	112
10.1.2.6 <code>CPLCleanTrailingSlash</code>	112
10.1.2.7 <code>CPLCloseShared</code>	113
10.1.2.8 <code>CPLCorrespondingPaths</code>	113
10.1.2.9 <code>CPLDecToPackedDMS</code>	113
10.1.2.10 <code>CPLDumpSharedList</code>	114
10.1.2.11 <code>CPLExtractRelativePath</code>	114
10.1.2.12 <code>CPLFGets</code>	114
10.1.2.13 <code>CPLFormCIFilename</code>	114
10.1.2.14 <code>CPLFormFilename</code>	115
10.1.2.15 <code>CPLGenerateTempFilename</code>	115
10.1.2.16 <code>CPLGetBasename</code>	115
10.1.2.17 <code>CPLGetConfigOption</code>	116
10.1.2.18 <code>CPLGetCurrentDir</code>	116
10.1.2.19 <code>CPLGetDirname</code>	116
10.1.2.20 <code>CPLGetExecPath</code>	117
10.1.2.21 <code>CPLGetExtension</code>	117
10.1.2.22 <code>CPLGetFilename</code>	117
10.1.2.23 <code>CPLGetPath</code>	118
10.1.2.24 <code>CPLGetSharedList</code>	118
10.1.2.25 <code>CPLGetSymbol</code>	118
10.1.2.26 <code>CPLIsFilenameRelative</code>	119
10.1.2.27 <code>CPLMalloc</code>	119
10.1.2.28 <code>CPLOpenShared</code>	120
10.1.2.29 <code>CPLPackedDMSToDec</code>	120
10.1.2.30 <code>CPLPrintDouble</code>	121
10.1.2.31 <code>CPLPrintInt32</code>	121
10.1.2.32 <code>CPLPrintPointer</code>	121
10.1.2.33 <code>CPLPrintString</code>	122
10.1.2.34 <code>CPLPrintStringFill</code>	122
10.1.2.35 <code>CPLPrintTime</code>	122
10.1.2.36 <code>CPLPrintUIntBig</code>	123

10.1.2.37 CPLProjectRelativeFilename	123
10.1.2.38 CPLReadLine	124
10.1.2.39 CPLReadLine2L	124
10.1.2.40 CPLReadLineL	124
10.1.2.41 CPLRealloc	125
10.1.2.42 CPLResetExtension	125
10.1.2.43 CPLScanDouble	125
10.1.2.44 CPLScanLong	125
10.1.2.45 CPLScanPointer	126
10.1.2.46 CPLScanString	126
10.1.2.47 CPLScanUIntBig	126
10.1.2.48 CPLScanULong	127
10.1.2.49 CPLSetConfigOption	127
10.1.2.50 CPLSetThreadLocalConfigOption	127
10.1.2.51 CPLStrdup	128
10.1.2.52 CPLStrlwr	128
10.1.2.53 CPLStrtod	128
10.1.2.54 CPLStrtodDelim	128
10.1.2.55 CPLStrtof	129
10.1.2.56 CPLStrtofDelim	129
10.1.2.57 CPLUnlinkTree	129
10.2 cpl_error.h File Reference	130
10.2.1 Detailed Description	130
10.2.2 Function Documentation	130
10.2.2.1 _CPLAssert	130
10.2.2.2 CPLEmergencyError	130
10.2.2.3 CPLErrorReset	131
10.2.2.4 CPLGetErrorHandlerUserData	131
10.2.2.5 CPLGetLastErrorMsg	131
10.2.2.6 CPLGetLastErrorNo	131
10.2.2.7 CPLGetLastErrorType	131
10.2.2.8 CPLPopErrorHandler	132
10.2.2.9 CPLPushErrorHandler	132
10.2.2.10 CPLPushErrorHandlerEx	132
10.2.2.11 CPLSetErrorHandler	132
10.2.2.12 CPLSetErrorHandlerEx	133
10.3 cpl_hash_set.h File Reference	133
10.3.1 Detailed Description	134
10.3.2 Function Documentation	134
10.3.2.1 CPLHashSetDestroy	134

10.3.2.2	CPLHashSetEqualPointer	134
10.3.2.3	CPLHashSetEqualStr	134
10.3.2.4	CPLHashSetForEach	134
10.3.2.5	CPLHashSetHashPointer	135
10.3.2.6	CPLHashSetHashStr	135
10.3.2.7	CPLHashSetInsert	135
10.3.2.8	CPLHashSetLookup	135
10.3.2.9	CPLHashSetNew	136
10.3.2.10	CPLHashSetRemove	136
10.3.2.11	CPLHashSetSize	136
10.4	cpl_http.h File Reference	137
10.4.1	Detailed Description	137
10.4.2	Function Documentation	137
10.4.2.1	CPLHTTPDestroyResult	137
10.4.2.2	CPLHTTPEnabled	137
10.4.2.3	CPLHTTPFetch	138
10.4.2.4	CPLHTTPParseMultipartMime	138
10.5	cpl_list.h File Reference	138
10.5.1	Detailed Description	139
10.5.2	Typedef Documentation	139
10.5.2.1	CPLList	139
10.5.3	Function Documentation	139
10.5.3.1	CPLListAppend	139
10.5.3.2	CPLListCount	139
10.5.3.3	CPLListDestroy	140
10.5.3.4	CPLListGet	140
10.5.3.5	CPLListGetData	140
10.5.3.6	CPLListGetLast	140
10.5.3.7	CPLListGetNext	141
10.5.3.8	CPLListInsert	141
10.5.3.9	CPLListRemove	141
10.6	cpl_minixml.h File Reference	141
10.6.1	Detailed Description	142
10.6.2	Typedef Documentation	143
10.6.2.1	CPLXMLNode	143
10.6.3	Enumeration Type Documentation	143
10.6.3.1	CPLXMLNodeType	143
10.6.4	Function Documentation	143
10.6.4.1	CPLAddXMLChild	143
10.6.4.2	CPLAddXMLSibling	143

10.6.4.3 CPLCleanXMLElementName	144
10.6.4.4 CPLCloneXMLTree	144
10.6.4.5 CPLCreateXMLElementAndValue	144
10.6.4.6 CPLCreateXMLNode	145
10.6.4.7 CPLDestroyXMLNode	145
10.6.4.8 CPLGetXMLNode	145
10.6.4.9 CPLGetXMLValue	146
10.6.4.10 CPLParseXMLFile	146
10.6.4.11 CPLParseXMLString	146
10.6.4.12 CPLRemoveXMLChild	147
10.6.4.13 CPLSearchXMLNode	147
10.6.4.14 CPLSerializeXMLTree	147
10.6.4.15 CPLSerializeXMLTreeToFile	148
10.6.4.16 CPLSetXMLValue	148
10.6.4.17 CPLStripXMLNamespace	148
10.7 cpl_odbc.h File Reference	149
10.7.1 Detailed Description	149
10.8 cpl_port.h File Reference	149
10.8.1 Detailed Description	149
10.8.2 Macro Definition Documentation	149
10.8.2.1 CPL_LSBINT16PTR	149
10.8.2.2 CPL_LSBINT32PTR	150
10.9 cpl_quad_tree.h File Reference	150
10.9.1 Detailed Description	150
10.9.2 Function Documentation	150
10.9.2.1 CPLQuadTreeCreate	150
10.9.2.2 CPLQuadTreeDestroy	151
10.9.2.3 CPLQuadTreeForeach	151
10.9.2.4 CPLQuadTreeGetAdvisedMaxDepth	151
10.9.2.5 CPLQuadTreeInsert	151
10.9.2.6 CPLQuadTreeSearch	151
10.9.2.7 CPLQuadTreeSetBucketCapacity	152
10.9.2.8 CPLQuadTreeSetMaxDepth	152
10.10 cpl_string.h File Reference	152
10.10.1 Detailed Description	153
10.10.2 Function Documentation	153
10.10.2.1 CPLBinaryToHex	153
10.10.2.2 CPLEncodingCharSize	154
10.10.2.3 CPLEscapeString	154
10.10.2.4 CPLForceToASCII	155

10.10.2.5 CPLGetValueType	155
10.10.2.6 CPLHexToBinary	155
10.10.2.7 CPLIsUTF8	156
10.10.2.8 CPLParseNameValue	156
10.10.2.9 CPLRecode	156
10.10.2.10 CPLRecodeFromWChar	157
10.10.2.11 CPLRecodeToWChar	157
10.10.2.12 CPLStrlcat	158
10.10.2.13 CPLStrlcpy	158
10.10.2.14 CPLStrnlen	159
10.10.2.15 CPLUnescapeString	159
10.10.2.16 CSLCount	159
10.10.2.17 CSLDestroy	160
10.10.2.18 CSLDuplicate	160
10.10.2.19 CSLFindName	160
10.10.2.20 CSLFindString	160
10.10.2.21 CSLLoad	161
10.10.2.22 CSLLoad2	161
10.10.2.23 CSLMerge	161
10.10.2.24 CSLPartialFindString	162
10.10.2.25 CSLSetNameValue	162
10.10.2.26 CSLSetNameValueSeparator	162
10.10.2.27 CSLTestBoolean	163
10.10.2.28 CSLTokenizeString2	163
10.11 cpl_vsi.h File Reference	164
10.11.1 Detailed Description	165
10.11.2 Function Documentation	165
10.11.2.1 VSIFCloseL	165
10.11.2.2 VSIFEofL	166
10.11.2.3 VSIFFlushL	166
10.11.2.4 VSIFFileFromMemBuffer	166
10.11.2.5 VSIFOpenL	167
10.11.2.6 VSIFReadL	167
10.11.2.7 VSIFReadMultiRangeL	168
10.11.2.8 VSIFSeekL	168
10.11.2.9 VSIFTellL	168
10.11.2.10 VSIFTruncateL	169
10.11.2.11 VSIFWriteL	169
10.11.2.12 VSIGetMemFileBuffer	169
10.11.2.13 VSInstallGZipFileHandler	170

10.11.2.14VSIIInstallMemFileHandler	170
10.11.2.15VSIIInstallSparseFileHandler	171
10.11.2.16VSIIInstallStdinHandler	171
10.11.2.17VSIIInstallStdoutHandler	172
10.11.2.18VSIIInstallSubFileHandler	172
10.11.2.19VSIIInstallTarFileHandler	172
10.11.2.20VSIIInstallZipFileHandler	172
10.11.2.21VSIIIsCaseSensitiveFS	173
10.11.2.22VSIMalloc2	173
10.11.2.23VSIMalloc3	173
10.11.2.24VSIMkdir	174
10.11.2.25VSIReadDir	174
10.11.2.26VSIRename	174
10.11.2.27VSIRmdir	175
10.11.2.28VSIStatExL	175
10.11.2.29VSIStatL	175
10.11.2.30VSIUnlink	176
10.12sdtsdataset.cpp File Reference	176
10.12.1 Detailed Description	176

Chapter 1

ISO8211Lib

Introduction

ISO8211Lib is intended to be a simple reader for ISO/IEC 8211 formatted files, particularly those that are part of SDTS and S-57 datasets. It consists of open source, easy to compile and integrate C++ code.

ISO 8211 Background

The [ISO 8211 FAQ](#) has some good background on ISO 8211 formatted files. I will briefly introduce it here, with reference to the library classes representing the components.

An 8211 file ([DDFModule](#)) consists of a series of logical records. The first record is special, and is called the DDR (Data Description Record). It basically contains definitions of all the data objects (fields or [DDFFieldDefn](#) objects) that can occur on the following data records.

The remainder of the records are known as DRs (data records - [DDFRecord](#)). They each contain one or more field ([DDFField](#)) instances. What fields appear on what records is not defined by ISO 8211, though more specific requirements may be implied by a particular data standard such as SDTS or S-57.

Each field instance has a name, and consists of a series of subfields. A given field always has the same subfields in each field instance, and these subfields are defined in the DDR ([DDFSUBfieldDefn](#)), in association with their field definition ([DDFFieldDefn](#)). A field may appear 0, 1, or many times in a DR.

Each subfield has a name, format (from the [DDFSUBfieldDefn](#)) and actual subfield data for a particular DR. Some fields contain an *array* of their group of subfields. For instance a *coordinate field* may have X and Y subfields, and they may repeat many times within one coordinate field indicating a series of points.

This would be a real good place for a UML diagram of ISO 8211, and the corresponding library classes!

Development Information

The [iso8211.h](#) contains the definitions for all public ISO8211Lib classes, enumerations and other services.

To establish access to an ISO 8211 dataset, instantiate a [DDFModule](#) object, and then use the [DDFModule::Open\(\)](#) method. This will read the DDR, and establish all the [DDFFieldDefn](#), and [DDFSUBfieldDefn](#) objects which can be queried off the [DDFModule](#).

The use [DDFModule::ReadRecord\(\)](#) to fetch data records ([DDFRecord](#)). When a record is read, a list of field objects ([DDFField](#)) on that record are created. They can be queried with various [DDFRecord](#) methods.

Data pointers for individual subfields of a [DDFField](#) can be fetched with [DDFField::GetSubfieldData\(\)](#). The interpreted value can then be extracted with the appropriate one of [DDFSUBfieldDefn::ExtractIntValue\(\)](#), [DDFSUBfieldDefn::ExtractStringValue\(\)](#), or [DDFSUBfieldDefn::ExtractFloatValue\(\)](#). Note that there is no object instantiated for individual subfields of a [DDFField](#). Instead the application extracts a pointer to the subfields raw data, and then uses the [DDFSUBfieldDefn](#) for that subfield to extract a useable value from the raw data.

Once the end of the file has been encountered ([DDFModule::ReadRecord\(\)](#) returns NULL), the [DDFModule](#) should be deleted, which will close the file, and cleanup all records, definitions and related objects.

Class APIs

- [DDFModule](#) class.
- [DDFFieldDefn](#) class.
- [DDFSubfieldDefn](#) class.
- [DDFRecord](#) class.
- [DDFField](#) class.

A complete [Example Reader](#) should clarify simple use of ISO8211Lib.

Related Information

- The ISO 8211 standard can be ordered through [ISO](#). It cost me about \$200CDN.
- The [ISO/IEC 8211/DDFS Home Page](#) contains tutorials and some code by Dr. Alfred A. Brooks, one of the originators of the 8211 standard.
- The [ISO/IEC 8211 Home Page](#) has some python code for parsing 8211 files, and some other useful background.
- The [SDTS++](#) library from the USGS includes support for ISO 8211. It doesn't include some of the 1994 additions to ISO 8211, but it is sufficient for SDTS, and quite elegantly done. Also supports writing ISO 8211 files.
- The USGS also has an older [FIPS123](#) library which supports the older profile of ISO 8211 (to some extent).

Licensing

This library is offered as [Open Source](#). In particular, it is offered under the X Consortium license which doesn't attempt to impose any copyleft, or credit requirements on users of the code.

The precise license text is:

Copyright (c) 1999, Frank Warmerdam

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Building the Source

1. First, fetch the source. The most recent source should be accessible at an url such as <http://home.gdal.org/projects/iso8211/iso8211lib-1.4.zip>.

2. Untar the source.

```
% unzip iso8211lib-1.4.zip
```

3. On unix you can now type "configure" to establish configuration options.

4. On unix you can now type make to build libiso8211.a, and the sample mainline 8211view.

Windows developers will have to create their own makefile/project but can base it on the very simple Makefile.in provided. As well, you would need to copy cpl_config.h.in to [cpl_config.h](#), and modify as needed. The default will likely work OK, but may result in some compiler warnings. Let me know if you are having difficulties, and I will prepare a VC++ makefile.

Author and Acknowledgements

The primary author of ISO8211Lib is [Frank Warmerdam](#), and I can be reached at warmerdam@pobox.com. I am eager to receive bug reports, and also open to praise or suggestions.

I would like to thank:

- [Safe Software](#) who funded development of this library, and agreed for it to be Open Source.
- Mark Colletti, a primary author of SDTS++ from which I derived most of what I know about ISO 8211 and who was very supportive, answering a variety of questions.
- Tony J Ibbs, author of the ISO/IEC 8211 home page who answered a number of questions, and collected a variety of very useful information.
- Rodney Jenson, for a detailed bug report related to repeating variable length fields (from S-57).

I would also like to dedicate this library to the memory of Sol Katz. Sol released a variety of SDTS (and hence ISO8211) translators, at substantial personal effort, to the GIS community along with the many other generous contributions he made to the community. His example has been an inspiration to me, and I hope similar efforts on my part will contribute to his memory.

Chapter 2

sdts_al_main

<title>SDTS Abstraction Library</title>

Introduction

SDTS_AL, the SDTS Abstraction Library, is intended to be an relatively easy to use library for reading vector from SDTS TVP (Topological Vector Profile) files, primary DLG data from the USGS. It also include support for reading raster data such as USGS DEMs in SDTS format. It consists of open source, easy to compile and integrate C++ code.

SDTS Background

The USGS SDTS Page at <http://mcmcweb.er.usgs.gov/sdts> is the definitive source of information on the SDTS format. The SDTS format is based on the ISO 8211 encoding scheme for the underlying files, and the SDTS Abstraction Library uses ISO8211Lib library to decode them. All references to DDF* classes are from ISO8211Lib.

An SDTS Transfer is a grouping of ISO8211 encoded files (ending in the .DDF extension), normally with part of the basename in common. For instance a USGS DLG SDTS transfer might consists of many files matching the SC01????.DDF pattern. The key file in an SDTS transfer is the catalog file, such as SC01CATD.DDF.

Development Information

The `sdts_al.h` include file contains the definitions for all public SDTS classes, enumerations and other services.

The `SDTSTransfer` class is used to access a transfer as a whole. The `SDTSTransfer::Open()` method is passed the name of the catalog file, such as SC01CATD.DDF, to open.

The `SDTSTransfer` analyses the catalog, and some other aspects of the transfer, and builds a list of feature layers. This list can be accessed using the `SDTSTransfer::GetLayerCount()`, `SDTSTransfer::GetLayerType()`, and `SDTSTransfer::GetLayerIndexedReader()` methods. A typical TVP (Topological Vector Profile) transfer might include three point layers (of type SLTPoint), a line layer (of type SLTLine), a polygon layer (of type SLTPoly) as well as some additional attribute layers (of type SLTAttr). the `SDTSTransfer::GetLayerIndexedReader()` method can be used to instantiate a reader object for reading a particular layer. (NOTE: raster layers are handled differently).

Each type of `SDTSIndexedReader` (`SDTSPointReader`, `SDTSLineReader`, `SDTSPolygonReader`, and `SDTSArrReader`) returns specific subclasses of `SDTSIndexedFeature` from the `SDTSIndexedReader::GetNextFeature()` method. These classes are `SDTSRawPoint`, `SDTSRawLine`, `SDTSRawPolygon` and `SDTSArrRecord`. These classes can be investigated for details on the data available for each.

See the `SDTS_AL Tutorial` for more information on how to use this library.

Building the Source on Unix

1. First, fetch the source. The most recent source should be accessible at an url such as ftp://gdal.velocet.ca/pub/outgoing/sdts_1_3.tar.gz.
2. Unpack the source.

```
% gzip -d sdts_1_3.tar.gz
% tar xzvf sdts_1_3.tar.gz
```

3. Type "configure" to establish configuration options.
4. Type make to build sdts_al.a, and the sample mainline sdts2shp.

See the [SDTS_AL Tutorial](#) for more information on how to use this library.

Building the Source on Windows

1. First, fetch the source. The most recent source should be accessible at an url such as ftp://gdal.velocet.ca/pub/outgoing/sdts_1_3.zip.
2. Unpack the source.

```
C:> unzip sdts_1_3.zip
```

3. Build using makefile.vc with VC++. You will need the VC++ runtime environment variables (LIB/INCLUDE) set properly. This will build the library (sdts_al.lib), and the executables sdts2shp.exe, 8211view.exe and 8211dump.exe.

```
C:> nmake /f makefile.vc
```

See the [SDTS_AL Tutorial](#) for more information on how to use this library.

The sdts2shp Sample Program

The sdts2shp program distributed with this toolkit is primary intended to serve as an example of how to use the SDTS access library. However, it can be useful to translate SDTS datasets into ESRI Shapefile format.

```
Usage: sdts2shp CATD_filename [-o shapefile_name]
      [-m module_name] [-v]
```

Modules include 'LE01', 'PC01', 'NP01' and 'ARDF'

A typical session in which we inspect the contents of a transfer, and then extract polygon and line layers might look like this:

```
warmerda[134]% sdts2shp data/SC01CATD.DDF -v
Layers:
ASCF: 'Attribute Primary'
AHDR: 'Attribute Primary'
NP01: 'Point-Node'
NA01: 'Point-Node'
NO01: 'Point-Node'
LE01: 'Line'
PC01: 'Polygon'

warmerda[135)% sdts2shp data/SC01CATD.DDF -m PC01 -o pc01.shp
warmerda[136)% sdts2shp data/SC01CATD.DDF -m LE01 -o le01.shp
```

A [prebuilt executable](#) is available for Windows.

Licensing

This library is offered as [Open Source](#). In particular, it is offered under the X Consortium license which doesn't attempt to impose any copyleft, or credit requirements on users of the code.

The precise license text is:

Copyright (c) 1999, Frank Warmerdam

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author and Acknowledgements

The primary author of SDTS_AL is [Frank Warmerdam](#), and I can be reached at warmingdam@pobox.com. I am eager to receive bug reports, and also open to praise or suggestions.

I would like to thank:

- [Safe Software](#) who funded development of this library, and agreed for it to be Open Source.
- Mark Colletti, a primary author of [SDTS++](#) from which I derived most of what I know about SDTS and ISO8211 and who was very supportive, answering a variety of questions.

I would also like to dedicate this library to the memory of Sol Katz. Sol released a variety of SDTS translators, at substantial personal effort, to the GIS community along with the many other generous contributions he made to the community. His example has been an inspiration to me, and I hope similar efforts on my part will contribute to his memory.

Chapter 3

SDTS_AL_TUT

```
<title>SDTS Abstraction Library Tutorial</title>
```

This page is a walk through of the polygon layer portion of the [sdts2shp.cpp](#) example application. It is should give sufficient information to utilize the SDTS_AL library to read SDTS files.

Opening the Transfer

The following statements will open an SDTS transfer. The filename passed to [SDTSTransfer::Open\(\)](#) should be the name of the catalog file, such as `palo_alto/SC01CATD.DDF`. The `Open()` method returns `FALSE` if it fails for any reason. In addition to the message we print out ourselves, the [SDTSTransfer::Open\(\)](#) method will also emit it's own error message using `CPLError()`. See the [cpl_error.h](#) page for more information on how to capture and control `CPLError()` style error reporting.

```
#include "stds_al.h"

...
SDTSTransfer oTransfer;

if( !oTransfer.Open( pszCATDFilename ) )
{
    fprintf( stderr,
        "Failed to read CATD file '%s'\n",
        pszCATDFilename );
    exit( 100 );
}
```

Getting a Layer List

Once an [SDTSTransfer](#) has been opened, it is possible to establish what layers are available. The `sdts2shp` example problem includes a `-v` argument to dump a list of available layers. It isn't normally necessary to use the [SDTS_CATD](#) (catalog) from an application to access SDTS files; however, in this example we use it to fetch a module name, and description for each of the available layers.

In particular, the `SDTSTransfer::GetLayerCount()` method returns the number of feature layers in the transfer and the `SDTSTransfer::GetLayerCATDEntry()` is used to translate layer indexes into [SDTS_CATD](#) compatible CATD indexes.

```
printf( "Layers:\n" );
for( i = 0; i < oTransfer.GetLayerCount(); i++ )
{
    int          iCATDEntry = oTransfer.GetLayerCATDEntry(i);
```

```

        printf( " %s: '%s'\n",
            oTransfer.GetCATD() ->GetEntryModule(iCATDEntry),
            oTransfer.GetCATD() ->GetEntryTypeDesc(iCATDEntry) );
    }
    printf( "\n" );
}

```

The following would be a typical layer list. Note that there are many other modules (files) registered with the catalog, but only these ones are considered to be feature layers by the [SDTSTransfer](#) object. The rest are supporting information, much of it, like data quality, is ignored by the SDTS_AL library.

```

warmerda-c[113]% sdts2shp data/SC01CATD.DDF -v
Layers:
ASCF: 'Attribute Primary      '
AHDR: 'Attribute Primary      '
NP01: 'Point-Node             '
NA01: 'Point-Node             '
NO01: 'Point-Node             '
LE01: 'Line                   '
PC01: 'Polygon                '

```

Getting a Reader

In order to read polygon features, it is necessary to instantiate a polygon reader on the desired layer. The `sdts2shp.cpp` program allow the user to select a module name (such as PC01, stored in `pszMODN`) to write to shape format. Other application might just search for, and operate on all known layers of a desired type.

The [SDTSTransfer::GetLayerIndexedReader\(\)](#) method instantiates a reader of the desired type. In this case we know we are instantiating a [SDTSPolygonReader](#) so we can safely cast the returned [SDTSIndexedReader](#) pointer to the more specific type [SDTSPolygonReader](#).

```

SDTSPolygonReader *poPolyReader;

poPolyReader = (SDTSPolygonReader *) 
    poTransfer->GetLayerIndexedReader( poTransfer->FindLayer( pszMODN ) );

if( poPolyReader == NULL )
{
    fprintf( stderr, "Failed to open %s.\n",
        poTransfer->GetCATD() ->GetModuleFilePath( pszMODN ) );
    return;
}

```

Note that readers returned by [SDTSTransfer::GetLayerIndexedReader\(\)](#) are managed by the [SDTSTransfer](#), and should not be deleted by the application.

Collecting Polygon Geometry

The SDTS TVP format does not directly associate a polygons geometry (the points forming it's boundary) with the polygon feature. Instead it is stored in separate line layers, and the lines contain references to the right, and left polygons that the lines border.

The SDTS_AL library provides a convenient method for forming the polygon geometry. Basically just call the [SDTSPolygonReader::AssemblePolygons\(\)](#) method. This method will scan all SLTLine layers in the transfer, indexing them and attaching their line work to the polygons. Then it assembles the line work into rings. It also ensures that the outer ring comes first, that the outer ring is counter-clockwise and that the inner ring(s) are clockwise.

```
poPolyReader->AssembleRings( poTransfer );
```

Upon completion the [SDTSPolygonReader](#) will have been "indexed". That means that all the polygon information will have been read from disk, and the polygon objects will now have information stored with them indicating the list of edges that form their border.

Identifying Attributes

In order to create the schema for the output shapefile dataset, it is necessary to identify the attributes associated with the polygons. There are two types of attributes which can occur. The first are hardcoded attributes specific to the feature type, and the second are generic user attributes stored in a separate primary attribute layer.

In the case of [SDTSRawPolygon](#), there is only one attribute of interest, and that is the record number of the polygon. This is actually stored within the oModId data member of the [SDTSIndexedFeature](#) base class, as will be seen in later examples when we write it to disk. For now we create a DBF field for the record number. This record number is a unique identifier of the polygon within this module/layer.

```
nSDTSRecordField = DBFAddField( hDBF, "SDTSRecId", FTInteger, 8, 0 );
```

Identification of user attributes is more complicated. Any feature in a layer can have associates with 0, 1, 2 or potentially more attribute records in other primary attribute layers. In order to establish a schema for the layer it is necessary to build up a list of all attribute layers (tables) to which references appear. The [SDTSIndexedReader::ScanModuleReferences\(\)](#) method can be used to scan a whole module for references to attribute modules via the ATID field. The return result is a list of referenced modules in the form of a string list. In a typical case this is one or two modules, such as "ASCF".

```
char **papszModRefs = poPolyReader->ScanModuleReferences();
```

In [sdts2shp.cpp](#), a subroutine ([AddPrimaryAttrToDBFSchema\(\)](#)) is defined to add all the fields of all references attribute layers to the DBF file. For each module in the list the following steps are executed.

Fetch an Attribute Module Reader

The following code is similar to our code for create a polygon layer reader. It creates a reader on one of the attribute layers referenced. We explicitly rewind it since it may have been previously opened and read by another part of the application.

```
SDTSAttrReader *poAttrReader;

poAttrReader = (SDTSAttrReader *) 
    poTransfer->GetLayerIndexedReader(
        poTransfer->FindLayer( papszModuleList[iModule] ) );

if( poAttrReader == NULL )
{
    printf( "Unable to open attribute module %s, skipping.\n" ,
        papszModuleList[iModule] );
    continue;
}

poAttrReader->Rewind();
```

Get a Prototype Record

In order to get access to field definitions, and in order to establish some sort of reasonable default lengths for field without fixed lengths the [sdts2shp](#) program fetches a prototype record from the attribute module.

```
SDTSAttrRecord *poAttrFeature;
```

```

    poAttrFeature = (SDTSAttrRecord *) poAttrReader->GetNextFeature();
    if( poAttrFeature == NULL )
    {
        fprintf( stderr,
            "Didn't find any meaningful attribute records in %s.\n",
            papszModuleList[iModule] );

        continue;
    }
}

```

When no longer needed, the attribute record may need to be explicitly deleted if it is not part of an indexed cached.

```

if( !poAttrReader->IsIndexed() )
    delete poAttrFeature;
}

```

Extract Field Definitions

The Shapefile DBF fields are defined based on the information available for each of the subfields of the attribute records ATTR [DDFField](#) (the poATTR data member). The following code loops over each of the subfields, getting a pointer to the DDBSubfieldDefn containing information about that subfield.

```

DDFFieldDefn      *poFDefn = poAttrFeature->poATTR->GetFieldDefn();
int               iSF;
DDFField         *poSR = poAttrFeature->poATTR;

for( iSF=0; iSF < poFDefn->GetSubfieldCount(); iSF++ )
{
    DDFSubfieldDefn      *poSFDefn = poFDefn->GetSubfield( iSF );
}

```

Then each of the significant ISO8211 field types is translated to an appropriate DBF field type. In cases where the nWidth field is zero, indicating that the field is variable width, we use the length of the field in the prototype record. Ideally we would scan the whole file to find the longest value for each field, but that would be a significant amount of work.

```

int           nWidth = poSFDefn->GetWidth();

switch( poSFDefn->GetType() )
{
    case DDFString:
        if( nWidth == 0 )
        {
            int           nMaxBytes;

            const char * pachData = poSR->GetSubfieldData(poSFDefn,
                                                &nMaxBytes);

            nWidth = strlen(poSFDefn->ExtractStringData(pachData,
                                                nMaxBytes, NULL ));
        }

        DBFAAddField( hDBF, poSFDefn->GetName(), FTString, nWidth, 0 );
        break;

    case DDFInt:
        if( nWidth == 0 )
            nWidth = 9;
}

```

```

DBFAddField( hDBF, poSFDefn->GetName(), FTInteger, nWidth, 0 );
break;

case DDFFloat:
    DBFAddField( hDBF, poSFDefn->GetName(), FTDouble, 18, 6 );
break;

default:
    fprintf( stderr,
        "Dropping attribute '%s' of module '%s'. "
        "Type unsupported\n",
        poSFDefn->GetName(),
        papszModuleList[iModule] );
break;
}
}
}

```

Reading Polygon Features

With definition of the attribute schema out of the way, we return to the main event, reading polygons from the polygon layer. We have already instantiated the [SDTSPolygonReader](#) (poPolyReader), and now we loop reading features from it. Note that we `Rewind()` the reader to ensure we are starting at the beginning. After we are done process the polygon we delete it, if and only if the layer does not have an index cache.

```

SDTSRawPolygon      *poRawPoly;

poPolyReader->Rewind();
while( (poRawPoly = (SDTSRawPolygon *) poPolyReader->GetNextFeature()) != NULL )
{
    ... process and write polygon ...

    if( !poPolyReader->IsIndexed() )
        delete poRawPoly;
}

```

Translate Geometry

In an earlier step we used the [SDTSPolygonReader::AssembleRings\(\)](#) method to build ring geometry on the polygons from the linework in the line layers.

Coincidentally (well, ok, maybe it isn't a coincidence) it so happens that the ring organization exactly matches what is needed for the shapefile api. The following call creates a polygon from the ring information in the [SDTSRawPolygon](#). See the [SDTSRawPolygon](#) reference help for a fuller definition of the nRings, panRingStart, nVertices, and vertex fields.

```

psShape = SHPCreateObject( SHPT_POLYGON, -1, poRawPoly->nRings,
                           poRawPoly->panRingStart, NULL,
                           poRawPoly->nVertices,
                           poRawPoly->padfX,
                           poRawPoly->padfY,
                           poRawPoly->padfZ,
                           NULL );

```

Write Record Number

The following call is used to write out the record number of the polygon, fetched from the [SDTSIndexedFeature::oModId](#) data member. The szModule value in this data field will always match the module name for the whole layer.

While not shown here, there is also an szOBRP field on oModId which have different values depending on whether the polygon is a universe or regular polygon.

```
DBFWriteIntegerAttribute( hDBF, iShape, nSDTSRecordField,
                          poRawPoly->oModId.nRecord );
```

Fetch Associated User Records

In keeping with the setting up of the schema, accessing the user records is somewhat complicated. In sdts2shp, the primary attribute records associated with any feature (including SDTSRawPolygons) can be fetched with the WriteAttrRecordToDBF() function defined as follows.

In particular, the poFeature->nAttributes member indicates how many associated attribute records there are. The poFeature->aoATID[] array contains the **SDTSMoid**'s for each record. This **SDTSMoid** can be passed to **SDTSTransfer::GetAttr()** to fetch the **DDFField** pointer for the user attributes. The WriteAttrRecordToDBF() method is specific to sdts2shp and will be define later.

```
int          iAttrRecord;

for( iAttrRecord = 0; iAttrRecord < poFeature->nAttributes; iAttrRecord++ )
{
    DDFField      *poSR;

    poSR = poTransfer->GetAttr( poFeature->aoATID+iAttrRecord );

    WriteAttrRecordToDBF( hDBF, iRecord, poTransfer, poSR );
}
```

Write User Attributes

In a manner analogous to the definition of the fields from the prototype attribute record, the following code loops over the subfields, and fetches the data for each. The data extraction via poSR->GetSubfieldData() is a bit involved, and more information can be found on the **DDFField** reference page.

```
/* -----
/*      Process each subfield in the record.          */
/* ----- */
DDFFieldDefn      *poFDefn = poSR->GetFieldDefn();

for( int iSF=0; iSF < poFDefn->GetSubfieldCount(); iSF++ )
{
    DDFSubfieldDefn *poSFDefn = poFDefn->GetSubfield( iSF );
    int              iField;
    int              nMaxBytes;
    const char *     pachData = poSR->GetSubfieldData(poSFDefn,
                                                       &nMaxBytes);

/* -----
/*      Identify the related DBF field, if any.        */
/* ----- */
for( iField = 0; iField < hDBF->nFields; iField++ )
{
    if( EQUALN(poSFDefn->GetName(),
               hDBF->pszHeader+iField*32,10) )
        break;
}
```

```

if( iField == hDBF->nFields )
    iField = -1;

/* -----
   *      Handle each of the types.
   * -----
switch( poSFDefn->GetType() )
{
    case DDFString:
        const char *pszValue;

        pszValue = poSFDefn->ExtractStringData(pachData, nMaxBytes,
                                                NULL);

        if( iField != -1 )
            DBFWriteStringAttribute(hDBF, iRecord, iField, pszValue );
        break;

    case DDFFloat:
        double dfValue;

        dfValue = poSFDefn->ExtractFloatData(pachData, nMaxBytes,
                                                NULL);

        if( iField != -1 )
            DBFWriteDoubleAttribute( hDBF, iRecord, iField, dfValue );
        break;

    case DDFInt:
        int nValue;

        nValue = poSFDefn->ExtractIntData(pachData, nMaxBytes, NULL);

        if( iField != -1 )
            DBFWriteIntegerAttribute( hDBF, iRecord, iField, nValue );
        break;

    default:
        break;
}
} /* next subfield */

```

Cleanup

In the case of sdts2shp, the [SDTSTransfer](#) is created on the stack. When it falls out of scope it is destroyed, and all the indexed readers, and their indexed features caches are also cleaned up.

Chapter 4

sdts2shp.cpp

```
<title>SDTS To Shape Example Application</title>

/*
 * $Id: sdts2shp.cpp 19952 2010-07-02 05:44:18Z warmerdam $
 *
 * Project: SDTS Translator
 * Purpose: Mainline for converting to ArcView Shapefiles.
 * Author: Frank Warmerdam, warmerdam@pobox.com
 *
 ****
 * Copyright (c) 1999, Frank Warmerdam
 *
 * Permission is hereby granted, free of charge, to any person obtaining a
 * copy of this software and associated documentation files (the "Software"),
 * to deal in the Software without restriction, including without limitation
 * the rights to use, copy, modify, merge, publish, distribute, sublicense,
 * and/or sell copies of the Software, and to permit persons to whom the
 * Software is furnished to do so, subject to the following conditions:
 *
 * The above copyright notice and this permission notice shall be included
 * in all copies or substantial portions of the Software.
 *
 * THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS
 * OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY,
 * FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL
 * THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER
 * LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING
 * FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER
 * DEALINGS IN THE SOFTWARE.
 ****/
#include "sdts_al.h"
#include "shapefil.h"
#include "cpl_string.h"

CPL_CVSID("$Id: sdts2shp.cpp 19952 2010-07-02 05:44:18Z warmerdam $");

static int bVerbose = FALSE;

static void WriteLineShapefile( const char *, SDTSTransfer *,
                               const char * );
static void WritePointShapefile( const char *, SDTSTransfer *,
                                 const char * );
static void WriteAttributeDBF( const char *, SDTSTransfer *,
                               const char * );
static void WritePolygonShapefile( const char *, SDTSTransfer *,
                                   const char * );

static void
AddPrimaryAttrToDBFSchema( DBFHandle hDBF, SDTSTransfer *
                           poTransfer,
                           char ** papszModuleList );
static void
WritePrimaryAttrToDBF( DBFHandle hDBF, int nRecord,
                       SDTSTransfer *, SDTSFeature *
                           poFeature );
static void
WriteAttrRecordToDBF( DBFHandle hDBF, int nRecord,
                      SDTSTransfer *, DDFField *
                           poAttributes );

/*
 ****
 * Usage()
 */
```

```

/*
 * ****
 */

static void Usage()
{
    printf( "Usage: sdts2shp CATD_filename [-o shapefile_name]\n"
            "      [-m module_name] [-v]\n"
            "\n"
            "Modules include 'LE01', 'PC01', 'NP01' and 'ARDF'\n" );
    exit( 1 );
}

/*
 * ****
 * main()
 * ****
 */

int main( int nArgc, char ** papszArgv )
{
{
    int         i;
    const char *pszCATDFilename = NULL;
    const char *pszMODN = "LE01";
    char        *pszShapefile = "sdts_out.shp";
    SDTSTransfer oTransfer;

/*
 * -----
 * Interpret commandline switches.
 * -----
 */
    if( nArgc < 2 )
        Usage();

    pszCATDFilename = papszArgv[1];

    for( i = 2; i < nArgc; i++ )
    {
        if( EQUAL(papszArgv[i],"-m") && i+1 < nArgc )
            pszMODN = papszArgv[++i];
        else if( EQUAL(papszArgv[i],"-o") && i+1 < nArgc )
            pszShapefile = papszArgv[++i];
        else if( EQUAL(papszArgv[i],"-v") )
            bVerbose = TRUE;
        else
        {
            printf( "Incomplete, or unsupported option '%s'\n\n",
                    papszArgv[i] );
            Usage();
        }
    }

/*
 * -----
 * Massage shapefile name to have no extension.
 * -----
 */
    pszShapefile = strdup( pszShapefile );
    for( i = strlen(pszShapefile)-1; i >= 0; i-- )
    {
        if( pszShapefile[i] == '.' )
        {
            pszShapefile[i] = '\0';
            break;
        }
        else if( pszShapefile[i] == '/' || pszShapefile[i] == '\\')
            break;
    }

/*
 * -----
 * Open the transfer.
 * -----
 */
    if( !oTransfer.Open( pszCATDFilename ) )
    {
        fprintf( stderr,
                "Failed to read CATD file '%s'\n",
                pszCATDFilename );
        exit( 100 );
    }

/*
 * -----
 * Dump available layer in verbose mode.
 * -----
 */
    if( bVerbose )
    {
        printf( "Layers:\n" );
        for( i = 0; i < oTransfer.GetLayerCount(); i++ )
        {
            int          iCATDEntry = oTransfer.GetLayerCATDEntry

```

```

        (i);

        printf( " %s: '%s'\n",
               oTransfer->GetCATD()->GetEntryModule(iCATDEntry),
               oTransfer->GetCATD()->GetEntryTypeDesc
               (iCATDEntry) );
    }
    printf( "\n" );
}

/* -----
/*     Check that module exists. */
/* -----
if( oTransfer->FindLayer( pszMODN ) == -1 )
{
    fprintf( stderr, "Unable to identify module: %s\n", pszMODN );
    exit( 1 );
}

/* -----
/*     If the module is an LE module, write it to an Arc file. */
/* -----
if( pszMODN[0] == 'L' || pszMODN[0] == 'l' )
{
    WriteLineShapefile( pszShapefile, &oTransfer, pszMODN );
}

/* -----
/*     If the module is an attribute primary one, dump to DBF. */
/* -----
else if( pszMODN[0] == 'A' || pszMODN[0] == 'a'
        || pszMODN[0] == 'B' || pszMODN[0] == 'b' )
{
    WriteAttributeDBF( pszShapefile, &oTransfer, pszMODN );
}

/* -----
/*     If the module is a point one, dump to Shapefile. */
/* -----
else if( pszMODN[0] == 'N' || pszMODN[0] == 'n' )
{
    WritePointShapefile( pszShapefile, &oTransfer, pszMODN );
}

/* -----
/*     If the module is a polygon one, dump to Shapefile. */
/* -----
else if( pszMODN[0] == 'P' || pszMODN[0] == 'p' )
{
    WritePolygonShapefile( pszShapefile, &oTransfer, pszMODN );
}

else
{
    fprintf( stderr, "Unrecognised module name: %s\n", pszMODN );
}

CPLFree( pszShapefile );
}

#endif DBMALLOC
    malloc_dump(1);
#endif
}

/* *****
/*      WriteLineShapefile()
/* *****

static void WriteLineShapefile( const char * pszShapefile,
                               SDTSTransfer * poTransfer,
                               const char * pszMODN )

{
    SDTSLineReader      *poLineReader;

/* -----
/*     Fetch a reference to the indexed Pointgon reader. */
/* -----
poLineReader = (SDTSLineReader *)
    poTransfer->GetLayerIndexedReader( poTransfer->
        FindLayer( pszMODN ) );

if( poLineReader == NULL )
{
    fprintf( stderr, "Failed to open %s.\n",
            poTransfer->GetCATD()->GetModuleFilePath( pszMODN ) );
    return;
}

```

```

}

poLineReader->Rewind();

/*
 *      Create the Shapefile.
 */
/*-----*/
SHPHandle hSHP;

hSHP = SHPCreate( pszShapefile, SHPT_ARC );
if( hSHP == NULL )
{
    fprintf( stderr, "Unable to create shapefile '%s'\n",
             pszShapefile );
    return;
}

/*
 *      Create the database file, and our basic set of attributes.
 */
/*-----*/
DBFHandle hDBF;
int nLeftPolyField, nRightPolyField;
int nStartNodeField, nEndNodeField, nSDTSRecordField;
char szDBFFilename[1024];

sprintf( szDBFFilename, "%s.dbf", pszShapefile );

hDBF = DBFCreate( szDBFFilename );
if( hDBF == NULL )
{
    fprintf( stderr, "Unable to create shapefile .dbf for '%s'\n",
             pszShapefile );
    return;
}

nSDTSRecordField = DBFAddField( hDBF, "SDTSRecId", FTInteger, 8, 0 );
nLeftPolyField = DBFAddField( hDBF, "LeftPoly", FTString, 12, 0 );
nRightPolyField = DBFAddField( hDBF, "RightPoly", FTString, 12, 0 );
nStartNodeField = DBFAddField( hDBF, "StartNode", FTString, 12, 0 );
nEndNodeField = DBFAddField( hDBF, "EndNode", FTString, 12, 0 );

char **papszModRefs = poLineReader->ScanModuleReferences
();
AddPrimaryAttrToDBFSchema( hDBF, poTransfer, papszModRefs );
CSLDestroy( papszModRefs );

/*
 *      Process all the line features in the module.
 */
/*-----*/
SDTRawLine *poRawLine;

while( (poRawLine = poLineReader->GetNextLine()) != NULL )
{
    int iShape;

/*
 *      Write out a shape with the vertices.
 */
/*-----*/
SHPObjec t *psShape;

psShape = SHPCreateSimpleObject( SHPT_ARC, poRawLine->nVertices
,
                               poRawLine->padfX, poRawLine->
                               padfY,
                               poRawLine->padfZ );

iShape = SHPWriteObject( hSHP, -1, psShape );
SHPDestroyObject( psShape );

/*
 *      Write out the attributes.
 */
/*-----*/
char szID[13];

DBFWriteIntegerAttribute( hDBF, iShape, nSDTSRecordField,
                          poRawLine->oModId.nRecord );

sprintf( szID, "%s:%ld",
        poRawLine->oLeftPoly.szModule,
        poRawLine->oLeftPoly.nRecord );
DBFWriteStringAttribute( hDBF, iShape, nLeftPolyField, szID );

sprintf( szID, "%s:%ld",
        poRawLine->oRightPoly.szModule,
        poRawLine->oRightPoly.nRecord );
DBFWriteStringAttribute( hDBF, iShape, nRightPolyField, szID );

```

```

        sprintf( szID, "%s:%ld",
                  poRawLine->oStartNode.szModule,
                  poRawLine->oStartNode.nRecord );
        DBFWriteStringAttribute( hDBF, iShape, nStartNodeField, szID );

        sprintf( szID, "%s:%ld",
                  poRawLine->oEndNode.szModule,
                  poRawLine->oEndNode.nRecord );
        DBFWriteStringAttribute( hDBF, iShape, nEndNodeField, szID );

        WritePrimaryAttrToDBF( hDBF, iShape, poTransfer, poRawLine );

        if( !poLineReader->IsIndexed() )
            delete poRawLine;
    }

/*
 *      Close, and cleanup.
 */
/*
DBFClose( hDBF );
SHPClose( hSHP );
}

/*
 * *****
 *      WritePointShapefile()
 * *****
 */

static void WritePointShapefile( const char * pszShapefile,
                                SDTSTransfer * poTransfer,
                                const char * pszMODN )

{
    SDTSPointReader     *poPointReader;

/*
 *      Fetch a reference to the indexed Pointgon reader.
 */
    poPointReader = (SDTSPointReader *)
        poTransfer->GetLayerIndexedReader( poTransfer->
            FindLayer( pszMODN ) );

    if( poPointReader == NULL )
    {
        fprintf( stderr, "Failed to open %s.\n",
                 poTransfer->GetCATD()->GetModuleFilePath( pszMODN ) );
        return;
    }

    poPointReader->Rewind();

/*
 *      Create the Shapefile.
 */
    SHPHandle     hSHP;

    hSHP = SHPCreate( pszShapefile, SHPT_POINT );
    if( hSHP == NULL )
    {
        fprintf( stderr, "Unable to create shapefile '%s'\n",
                 pszShapefile );
        return;
    }

/*
 *      Create the database file, and our basic set of attributes.
 */
    DBFHandle     hDBF;
    int          nAreaField, nSDTSRecordField;
    char         szDBFFilename[1024];

    sprintf( szDBFFilename, "%s.dbf", pszShapefile );

    hDBF = DBFCreate( szDBFFilename );
    if( hDBF == NULL )
    {
        fprintf( stderr, "Unable to create shapefile .dbf for '%s'\n",
                 pszShapefile );
        return;
    }

    nSDTSRecordField = DBFAAddField( hDBF, "SDTSRecId", FTInteger, 8, 0 );
    nAreaField = DBFAAddField( hDBF, "AreaId", FTString, 12, 0 );

    char **papszModRefs = poPointReader->ScanModuleReferences
        ();
    AddPrimaryAttrToDBFSchema( hDBF, poTransfer, papszModRefs );
}

```

```

    CSLDestroy( papszModRefs );

/* ===== */
/*      Process all the line features in the module.          */
/* ===== */
/* SDTSSRawPoint      *poRawPoint; */

while( (poRawPoint = poPointReader->GetNextPoint() != NULL )
{
    int             iShape;

/* ----- */
/*      Write out a shape with the vertices.                  */
/* ----- */
    SHPObject      *psShape;

    psShape = SHPCreateSimpleObject( SHPT_POINT, 1,
                                    &(poRawPoint->dfX),
                                    &(poRawPoint->dfY),
                                    &(poRawPoint->dfZ) );

    iShape = SHPWriteObject( hSHP, -1, psShape );

    SHPDestroyObject( psShape );

/* ----- */
/*      Write out the attributes.                            */
/* ----- */
/*      char      szID[13];

    DBFWriteIntegerAttribute( hDBF, iShape, nSDTSRecordField,
                           poRawPoint->oModId.nRecord );

    sprintf( szID, "%s:%ld",
            poRawPoint->oAreaId.szModule,
            poRawPoint->oAreaId.nRecord );
    DBFWriteStringAttribute( hDBF, iShape, nAreaField, szID );

    WritePrimaryAttrToDBF( hDBF, iShape, poTransfer, poRawPoint );

    if( !poPointReader->IsIndexed() )
        delete poRawPoint;
}

/* ----- */
/*      Close, and cleanup.                                */
/* ----- */
/*      DBFClose( hDBF );
    SHPClose( hSHP );
}

/* **** */
/*      WriteAttributeDBF()                               */
/* **** */

static void WriteAttributeDBF( const char * pszShapefile,
                             SDTSTransfer * poTransfer,
                             const char * pszMODN )

{
    SDTSArrReader     *poAttrReader;

/* ----- */
/*      Fetch a reference to the indexed Pointgon reader.   */
/* ----- */
    poAttrReader = (SDTSArrReader *)
        poTransfer->GetLayerIndexedReader( poTransfer->
        FindLayer( pszMODN ) );

    if( poAttrReader == NULL )
    {
        fprintf( stderr, "Failed to open %s.\n",
                poTransfer->GetCATD()->GetModuleFilePath( pszMODN ) );
        return;
    }

    poAttrReader->Rewind();

/* ----- */
/*      Create the database file, and our basic set of attributes. */
/* ----- */
/*      DBFHandle      hDBF;
    char            szDBFFilename[1024];

    sprintf( szDBFFilename, "%s.dbf", pszShapefile );
    hDBF = DBFCreate( szDBFFilename );
}

```

```

if( hDBF == NULL )
{
    fprintf( stderr, "Unable to create shapefile .dbf for '%s'\n",
             pszShapefile );
    return;
}

DBFAAddField( hDBF, "SDTSRecId", FTInteger, 8, 0 );

/*
 *      Prepare the schema.
 */
char **papszMODNList = CSLAddString( NULL, pszMODN );
AddPrimaryAttrToDBFSchema( hDBF, poTransfer, papszMODNList );
CSLDestroy( papszMODNList );

/*
 * =====
 *      Process all the records in the module.
 */
SDTSAttrRecord *poRecord;
int iRecord = 0;

while((poRecord = (SDTSAttrRecord*)poAttrReader->
       GetNextFeature()) != NULL)
{
    DBFWRITEintegerAttribute( hDBF, iRecord, 0,
                               poRecord->oModId.nRecord );

    WriteAttrRecordToDBF( hDBF, iRecord, poTransfer, poRecord->poATTR
    );

    if( !poAttrReader->IsIndexed() )
        delete poRecord;

    iRecord++;
}

/*
 *      Close, and cleanup.
 */
DBFClose( hDBF );
}

/*
 * ***** WritePolygonShapefile()
 * *****
 */

static void WritePolygonShapefile( const char * pszShapefile,
                                   SDTSTransfer * poTransfer,
                                   const char * pszMODN )

{
    SDTSPolygonReader *poPolyReader;

/*
 *      Fetch a reference to the indexed polygon reader.
 */
poPolyReader = (SDTSPolygonReader *)
    poTransfer->GetLayerIndexedReader( poTransfer->
    FindLayer( pszMODN ) );

if( poPolyReader == NULL )
{
    fprintf( stderr, "Failed to open %s.\n",
            poTransfer->GetCATD()->GetModuleFilePath( pszMODN ) );
    return;
}

/*
 *      Assemble polygon geometries from all the line layers.
 */
poPolyReader->AssembleRings( poTransfer, poTransfer->FindLayer
    (pszMODN) );

/*
 *      Create the Shapefile.
 */
SHPHandle hSHP;

hSHP = SHPCreate( pszShapefile, SHPT_POLYGON );
if( hSHP == NULL )
{
    fprintf( stderr, "Unable to create shapefile '%s'\n",
            pszShapefile );
    return;
}

```

```

}

/*
 *      Create the database file, and our basic set of attributes.
 */
DBFHandle    hDBF;
int          nSDTSRecordField;
char         szDBFFilename[1024];

sprintf( szDBFFilename, "%s.dbf", pszShapefile );

hDBF = DBFCreate( szDBFFilename );
if( hDBF == NULL )
{
    fprintf( stderr, "Unable to create shapefile .dbf for '%s'\n",
             pszShapefile );
    return;
}

nSDTSRecordField = DBFAddField( hDBF, "SDTSRecId", FTInteger, 8, 0 );

char **papszModRefs = poPolyReader->ScanModuleReferences
();
AddPrimaryAttrToDBFSchema( hDBF, poTransfer, papszModRefs );
CSLDestroy( papszModRefs );

/*
 *      Process all the polygon features in the module.
 */
SDTRawPolygon     *poRawPoly;

poPolyReader->Rewind();
while( (poRawPoly = (SDTRawPolygon *) poPolyReader->
GetNextFeature())
!= NULL )
{
    int           iShape;

/*
 *      Write out a shape with the vertices.
 */
SHPOBJECT        *psShape;

psShape = SHPCreateObject( SHPT_POLYGON, -1, poRawPoly->nRings,
                           poRawPoly->panRingStart, NULL,
                           poRawPoly->nVertices,
                           poRawPoly->padfX,
                           poRawPoly->padfY,
                           poRawPoly->padfZ,
                           NULL );

iShape = SHPWriteObject( hSHP, -1, psShape );

SHPDestroyObject( psShape );

/*
 *      Write out the attributes.
 */
DBFWriteIntegerAttribute( hDBF, iShape, nSDTSRecordField,
                           poRawPoly->oModId.nRecord );
WritePrimaryAttrToDBF( hDBF, iShape, poTransfer, poRawPoly );

if( !poPolyReader->IsIndexed() )
    delete poRawPoly;
}

/*
 *      Close, and cleanup.
 */
DBFClose( hDBF );
SHPClose( hSHP );
}

/*
 * ***** AddPrimaryAttrToDBF()
 */
/*
 *      Add the fields from all the given primary attribute modules
 *      to the schema of the passed DBF file.
 */
static void
AddPrimaryAttrToDBFSchema( DBFHandle hDBF, SDTSTransfer *poTransfer
,
                           char ** papszModuleList )

{
    for( int iModule = 0;

```

```

    papszModuleList != NULL && papszModuleList[iModule] != NULL;
    iModule++ )

    SDTSAttrReader *poAttrReader;

/* ----- */
/*      Get a reader on the desired module.          */
/* ----- */
    poAttrReader = (SDTSAttrReader *) poTransfer->GetLayerIndexedReader(
        poTransfer->FindLayer( papszModuleList[iModule] ) );

    if( poAttrReader == NULL )
    {
        printf( "Unable to open attribute module %s, skipping.\n" ,
            papszModuleList[iModule] );
        continue;
    }

    poAttrReader->Rewind();

/* ----- */
/*      Read the first record so we can clone schema information off      */
/*      of it.          */
/* ----- */
    SDTSAttrRecord *poAttrFeature;

    poAttrFeature = (SDTSAttrRecord *) poAttrReader->
GetNextFeature();
    if( poAttrFeature == NULL )
    {
        fprintf( stderr,
            "Didn't find any meaningful attribute records in %s.\n",
            papszModuleList[iModule] );

        continue;
    }

/* ----- */
/*      Clone schema off the first record. Eventually we need to          */
/*      get the information out of the DDR record, but it isn't           */
/*      clear to me how to accomplish that with the SDTS++ API.          */
/* ----- */
/*      The following approach may fail (dramatically) if some             */
/*      records do not include all subfields. Furthermore, no              */
/*      effort is made to make DBF field names unique. The SDTS            */
/*      attributes often have names much beyond the 14 character dbf        */
/*      limit which may result in non-unique attributes.                  */
/* ----- */
    DDFFieldDefn *poFDefn = poAttrFeature->poATTR->
GetFieldDefn();
    int iSF;
    DDFField *poSR = poAttrFeature->poATTR;

    for( iSF=0; iSF < poFDefn->GetSubfieldCount(); iSF++ )
    {
        DDFSubfieldDefn *poSFDefn = poFDefn->GetSubfield
(iSF);
        int nWidth = poSFDefn->GetWidth();

        switch( poSFDefn->GetType() )
        {
            case DDFString:
                if( nWidth == 0 )
                {
                    int nMaxBytes;

                    const char * pachData = poSR->GetSubfieldData
(poSFDefn,
                                         &nMaxBytes);

                    nWidth = strlen(poSFDefn->ExtractStringData
(pachData,
                                         nMaxBytes, NULL
));
                }
            case DDFInt:
                if( nWidth == 0 )
                nWidth = 9;

                DBFAddField( hDBF, poSFDefn->GetName(), FTString,
nWidth
, 0 );
                break;

            case DDFInt:
                if( nWidth == 0 )
                nWidth = 9;

                DBFAddField( hDBF, poSFDefn->GetName(), FTInteger,
nWidth, 0 );
        }
    }
}

```

```

        break;

    case DDFFloat:
        DBFAddField( hDBF, poSFDefn->GetName(), FTDouble, 18, 6
    );
        break;

    default:
        fprintf( stderr,
            "Dropping attribute '%s' of module '%s'.  "
            "Type unsupported\n",
            poSFDefn->GetName(),
            papszModuleList[ iModule ] );
        break;
    }
}

if( !poAttrReader->IsIndexed() )
    delete poAttrFeature;

} /* next module */
}

/* **** WritePrimaryAttrToDBF() ****/
/* **** Loop over all the attribute records linked to this feature. ****/
/* **** ===== */

static void
WritePrimaryAttrToDBF( DBFHandle hDBF, int iRecord,
                      SDTSTransfer * poTransfer, SDTSFeature
                      * poFeature )
{
/* ===== */
/* ===== Loop over all the attribute records linked to this feature. */
/* ===== */
int iAttrRecord;

for( iAttrRecord = 0; iAttrRecord < poFeature->nAttributes;
    iAttrRecord++ )
{
    DDFField *poSR;

    poSR = poTransfer->GetAttr( poFeature->paoATID+
        iAttrRecord );

    WriteAttrRecordToDBF( hDBF, iRecord, poTransfer, poSR );
}

/* **** WriteAttrRecordToDBF() ****/
/* **** ===== */

static void
WriteAttrRecordToDBF( DBFHandle hDBF, int iRecord,
                      SDTSTransfer * poTransfer, DDFField *
                      poSR )
{
/* -----
/* ----- Process each subfield in the record.
/* ----- */
DDFFieldDefn *poFDefn = poSR->GetFieldDefn()
;

for( int iSF=0; iSF < poFDefn->GetSubfieldCount(); iSF++ )
{
    DDFSubfieldDefn *poSFDefn = poFDefn->GetSubfield
    ( iSF );
    int iField;
    int nMaxBytes;
    const char * pachData = poSR->GetSubfieldData(
        poSFDefn,
        &nMaxBytes);

/* -----
/* ----- Identify the related DBF field, if any.
/* ----- */
for( iField = 0; iField < hDBF->nFields; iField++ )
{
    if( EQUALN(poSFDefn->GetName(),
              hDBF->pszHeader+iField*32, 10) )
        break;
}

if( iField == hDBF->nFields )

```

```

iField = -1;

/* -----
/*      Handle each of the types.
*/
/* -----
switch( poSFDefn->GetType() )
{
    case DDFString:
        const char *pszValue;

        pszValue = poSFDefn->ExtractStringData(pachData,
nMaxBytes,
                           NULL);

        if( iField != -1 )
            DBFWriteStringAttribute(hDBF, iRecord, iField, pszValue );
        break;

    case DDFFloat:
        double dfValue;

        dfValue = poSFDefn->ExtractFloatData(pachData,
nMaxBytes,
                           NULL);

        if( iField != -1 )
            DBFWriteDoubleAttribute( hDBF, iRecord, iField, dfValue );
        break;

    case DDFInt:
        int nValue;

        nValue = poSFDefn->ExtractIntData(pachData, nMaxBytes
, NULL);

        if( iField != -1 )
            DBFWriteIntegerAttribute( hDBF, iRecord, iField, nValue );
        break;

    default:
        break;
}
} /* next subfield */
}

```


Chapter 5

ISO8211_Example

```
/* ****
 * $Id: 8211view.cpp 10645 2007-01-18 02:22:39Z warmerdam $
 *
 * Project: SDTS Translator
 * Purpose: Example program dumping data in 8211 data to stdout.
 * Author: Frank Warmerdam, warmerdam@pobox.com
 *
 ****
 * Copyright (c) 1999, Frank Warmerdam
 *
 * Permission is hereby granted, free of charge, to any person obtaining a
 * copy of this software and associated documentation files (the "Software"),
 * to deal in the Software without restriction, including without limitation
 * the rights to use, copy, modify, merge, publish, distribute, sublicense,
 * and/or sell copies of the Software, and to permit persons to whom the
 * Software is furnished to do so, subject to the following conditions:
 *
 * The above copyright notice and this permission notice shall be included
 * in all copies or substantial portions of the Software.
 *
 * THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS
 * OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY,
 * FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL
 * THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER
 * LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING
 * FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER
 * DEALINGS IN THE SOFTWARE.
 ****/
#include <stdio.h>
#include "iso8211.h"

CPL_CVSID("$Id: 8211view.cpp 10645 2007-01-18 02:22:39Z warmerdam $");

static void ViewRecordField( DDFField * poField );
static int ViewSubfield( DDFSubfieldDefn *poSFDefn,
                        const char * pachFieldData,
                        int nBytesRemaining );

/* ****
 * main()
 * ****/
int main( int nArgc, char ** ppszArgv )

{
    DDFModule    oModule;
    const char   *pszFilename = NULL;
    int          bFSPTHack = FALSE;

    for( int iArg = 1; iArg < nArgc; iArg++ )
    {
        if( EQUAL(ppszArgv[iArg], "-fspt_repeating") )
            bFSPTHack = TRUE;
        else
            pszFilename = ppszArgv[iArg];
    }

    if( pszFilename == NULL )
    {
        printf( "Usage: 8211view filename\n" );
        exit( 1 );
    }
}
```

```

/*
 *-----*
 *      Open the file.  Note that by default errors are reported to      */
 *      stderr, so we don't bother doing it ourselves.                      */
/*-----*/
if( !oModule.Open( pszFilename ) )
{
    exit( 1 );
}

if( bFSPTHack )
{
    DDFFieldDefn *poFSPT = oModule.FindFieldDefn(
"FSPT" );

if( poFSPT == NULL )
    fprintf( stderr,
              "unable to find FSPT field to set repeating flag.\n" );
else
    poFSPT->SetRepeatingFlag( TRUE );
}

/*
 *-----*
 *      Loop reading records till there are none left.                  */
/*-----*/
DDFRecord *poRecord;
int iRecord = 0;

while( (poRecord = oModule.ReadRecord()) != NULL )
{
    printf( "Record %d (%d bytes)\n",
            ++iRecord, poRecord->GetDataSize() );

    /* -----*
     *      Loop over each field in this particular record.           */
    /*-----*/
    for( int iField = 0; iField < poRecord->GetFieldCount();
iField++ )
    {
        DDFField *poField = poRecord->GetField( iField )

        ViewRecordField( poField );
    }
}

/*
 *-----*
 *      ViewRecordField()                                              */
/*-----*/
/*      Dump the contents of a field instance in a record.             */
/*-----*/
static void ViewRecordField( DDFField * poField )
{
    int nBytesRemaining;
    const char *pachFieldData;
    DDFFieldDefn *poFieldDefn = poField->GetFieldDefn()
    ;

    // Report general information about the field.
    printf( "Field %s: %s\n",
            poFieldDefn->GetName(), poFieldDefn->GetDescription
            () );

    // Get pointer to this fields raw data.  We will move through
    // it consuming data as we report subfield values.

    pachFieldData = poField->GetData();
    nBytesRemaining = poField->GetDataSize();

    /* -----*
     *      Loop over the repeat count for this fields                 */
    /*      subfields.  The repeat count will almost                   */
    /*      always be one.                                            */
    /*-----*/
    int iRepeat;

    for( iRepeat = 0; iRepeat < poField->GetRepeatCount();
iRepeat++ )
    {

        /* -----*
         *      Loop over all the subfields of this field, advancing   */
         *      the data pointer as we consume data.                     */
        /*-----*/
    }
}

```

```

    int      iSF;

    for( iSF = 0; iSF < poFieldDefn->GetSubfieldCount();  

iSF++ )  

    {  

        DDFSubfieldDefn *poSFDefn = poFieldDefn->GetSubfield  

( iSF );  

        int          nBytesConsumed;  

        nBytesConsumed = ViewSubfield( poSFDefn, pachFieldData,  

nBytesRemaining );  

        nBytesRemaining -= nBytesConsumed;  

        pachFieldData += nBytesConsumed;  

    }  

}  

}  

/* ****  

/*      ViewSubfield()  

/* ****  

static int ViewSubfield( DDFSubfieldDefn *poSFDefn,  

                        const char * pachFieldData,  

                        int nBytesRemaining )  

{  

    int          nBytesConsumed = 0;  

    switch( poSFDefn->GetType() )  

    {  

        case DDFInt:  

            if( poSFDefn->GetBinaryFormat() == DDFSubfieldDefn::UInt )  

                printf( "      %s = %u\n",  

                        poSFDefn->GetName(),  

                        poSFDefn->ExtractIntData( pachFieldData,  

nBytesRemaining,  

                                         &nBytesConsumed ) );  

            else  

                printf( "      %s = %d\n",  

                        poSFDefn->GetName(),  

                        poSFDefn->ExtractIntData( pachFieldData,  

nBytesRemaining,  

                                         &nBytesConsumed ) );  

            break;  

        case DDFFloat:  

            printf( "      %s = %f\n",  

                    poSFDefn->GetName(),  

                    poSFDefn->ExtractFloatData( pachFieldData,  

nBytesRemaining,  

                                         &nBytesConsumed ) );  

            break;  

        case DDFString:  

            printf( "      %s = '%s'\n",  

                    poSFDefn->GetName(),  

                    poSFDefn->ExtractStringData( pachFieldData,  

nBytesRemaining,  

                                         &nBytesConsumed ) );  

            break;  

        case DDFBinaryString:  

        {  

            int   i;  

//rjensen 19-Feb-2002 5 integer variables to decode NAME and LNAM  

int vrid_rcnm=0;  

int vrid_rcid=0;  

int foид_agen=0;  

int foид_find=0;  

int foид_fids=0;  

GByte *pabyBString = (GByte *)  

poSFDefn->ExtractStringData( pachFieldData,  

nBytesRemaining,  

&nBytesConsumed );  

printf( "      %s = 0x", poSFDefn->GetName() );  

for( i = 0; i < MIN(nBytesConsumed,24); i++ )  

printf( "%02X", pabyBString[i] );  

if( nBytesConsumed > 24 )  

printf( "%s", "..." );  

// rjensen 19-Feb-2002 S57 quick hack. decode NAME and LNAM bitfields  

if ( EQUAL(poSFDefn->GetName(),"NAME") )  

{

```

```
vrid_rcnm=pabyBString[0];
vrid_rcid=pabyBString[1] + (pabyBString[2]*256) +
(pabyBString[3]*65536)+ (pabyBString[4]*16777216);
printf("\tVRID RCNM = %d,RCID = %u",vrid_rcnm,vrid_rcid);
}
else if ( EQUAL(poSFDefn->GetName(),"LNAM") )
{
    foid_agen=pabyBString[0] + (pabyBString[1]*256);
    foid_find=pabyBString[2] + (pabyBString[3]*256) +
(pabyBString[4]*65536)+ (pabyBString[5]*16777216);
    foid_fids=pabyBString[6] + (pabyBString[7]*256);
    printf("\tFOID AGEN = %u,FIDN = %u,FIDS = %u",
foid_agen,foid_find,foid_fids);
}

printf( "\n" );
break;
}

return nBytesConsumed;
}
```

Chapter 6

Class Index

6.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

_CPLHashSet	43
_CPLList	43
_CPLQuadTree	44
_QuadTreeNode	44
CPLErrorContext	44
CPLHTTPResult	44
CPLKeywordParser	45
CPLMimePart	45
CPLODBCDriverInstaller	46
CPLODBCSession	47
CPLODBCStatement	48
CPLRectObj	55
CPLSharedFileInfo	55
CPLStdCallThreadInfo	55
CPLXMLNode	55
ctb	56
curlfile_info	57
DDFField	57
DDFFieldDefn	59
DDFModule	61
DDFRecord	63
DDFSubfieldDefn	70
DefaultCSVFileNameTLS	74
errHandler	74
file_in_zip_read_info_s	74
FindFileTLS	74
GZipSnapshot	75
linkedlist_data_s	75
linkedlist_datablock_internal_s	75
ParseContext	75
SDTS_CATD	75
SDTS_CATDEntry	76
SDTS_IREF	76
SDTS_XREF	77
SDTSDataset	79
SDTSFeature	79
SDTSArrRecord	78
SDTSRawLine	87

SDTSRawPoint	89
SDTSRawPolygon	90
SDTSMIndexedReader	80
SDTSArrReader	77
SDTSLineReader	82
SDTSPointReader	84
SDTSPolygonReader	84
SDTSModId	83
SDTSSRasterBand	85
SDTSSRasterReader	85
SDTSTransfer	92
SFRegion	96
StackContext	96
tm_unz_s	96
tm_zip_s	96
unz_file_info_internal_s	96
unz_file_info_s	96
unz_file_pos_s	96
unz_global_info_s	96
unz_s	97
VSIArchiveContent	97
VSIArchiveEntry	97
VSIArchiveEntryFileOffset	97
VSITarEntryFileOffset	104
VSIZipEntryFileOffset	106
VSIArchiveReader	98
VSITarReader	104
VSIZipReader	107
VSICacheChunk	98
VSIFFileManager	99
VSIFFilesystemHandler	99
VSIArchiveFilesystemHandler	97
VSITarFilesystemHandler	104
VSIZipFilesystemHandler	106
VSIGZipFilesystemHandler	99
VSIMemFilesystemHandler	100
VSISparseFileFilesystemHandler	101
VSIStdinFilesystemHandler	101
VSIStdoutFilesystemHandler	102
VSIStdoutRedirectFilesystemHandler	103
VSISubFileFilesystemHandler	103
VSIUnixStdioFilesystemHandler	105
VSIMemFile	100
VSIVirtualHandle	105
VSIBufferedReaderHandle	98
VSICachedFile	98
VSIGZipHandle	100
VSIGZipWriteHandle	100
VSIMemHandle	101
VSISparseFileHandle	101
VSIStdinHandle	102
VSIStdoutHandle	102
VSIStdoutRedirectHandle	103
VSISubFileHandle	103
VSIUnixStdioHandle	105
VSIZipWriteHandle	107
zip_fileinfo	107

zip_internal	108
zlib_filefunc_def_s	108

Chapter 7

Class Index

7.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

_CPLHashSet	43
_CPLList	43
_CPLQuadTree	44
_QuadTreeNode	44
CPLErrorContext	44
CPLHTTPResult	44
CPLKeywordParser	45
CPLMimePart	45
CPLODBCDriverInstaller	46
CPLODBCSession	47
CPLODBCStatement	48
CPLRectObj	55
CPLSharedFileInfo	55
CPLStdCallThreadInfo	55
CPLXMLNode	55
ctb	56
curlfile_info	57
DDFField	57
DDFFieldDefn	59
DDFModule	61
DDFRecord	63
DDFSubfieldDefn	70
DefaultCSVFileNameTLS	74
errHandler	74
file_in_zip_read_info_s	74
FindFileTLS	74
GZipSnapshot	75
linkedlist_data_s	75
linkedlist_datablock_internal_s	75
ParseContext	75
SDTS_CATD	75
SDTS_CATDEntry	76
SDTS_IREF	76
SDTS_XREF	77
SDTSArrReader	77
SDTSArrRecord	78
SDTSDataset	79
SDTSFeature	79

SDTSIndexedReader	80
SDTSLineReader	82
SDTSMoId	83
SDTSPointReader	84
SDTSPolygonReader	84
SDTSRasterBand	85
SDTSRasterReader	85
SDTSRawLine	87
SDTSRawPoint	89
SDTSRawPolygon	90
SDTSTransfer	92
SFRegion	96
StackContext	96
tm_unz_s	96
tm_zip_s	96
unz_file_info_internal_s	96
unz_file_info_s	96
unz_file_pos_s	96
unz_global_info_s	96
unz_s	97
VSIArchiveContent	97
VSIArchiveEntry	97
VSIArchiveEntryFileOffset	97
VSIArchiveFilesystemHandler	97
VSIArchiveReader	98
VSIBufferedReaderHandle	98
VSICacheChunk	98
VSICachedFile	98
VSIFileManager	99
VSIFilesystemHandler	99
VSIGZipFilesystemHandler	99
VSIGZipHandle	100
VSIGZipWriteHandle	100
VSIMemFile	100
VSIMemFilesystemHandler	100
VSIMemHandle	101
VSISparseFileFilesystemHandler	101
VSISparseFileHandle	101
VSIStdinFilesystemHandler	101
VSIStdinHandle	102
VSIStdoutFilesystemHandler	102
VSIStdoutHandle	102
VSIStdoutRedirectFilesystemHandler	103
VSIStdoutRedirectHandle	103
VSISubFileFilesystemHandler	103
VSISubFileHandle	103
VSITarEntryFileOffset	104
VSITarFilesystemHandler	104
VSITarReader	104
VSIUnixStudioFilesystemHandler	105
VSIUnixStudioHandle	105
VSIVirtualHandle	105
VSIZipEntryFileOffset	106
VSIZipFilesystemHandler	106
VSIZipReader	107
VSIZipWriteHandle	107
zip_fileinfo	107
zip_internal	108

zlib_filefunc_def_s 108

Chapter 8

File Index

8.1 File List

Here is a list of all documented files with brief descriptions:

cpl_atomic_ops.h	??
cpl_config.h	??
cpl_config_extras.h	??
cpl_conv.h	109
cpl_csv.h	??
cpl_error.h	130
cpl_hash_set.h	133
cpl_http.h	137
cpl_list.h	138
cpl_minixml.h	141
cpl_minizip_ioapi.h	??
cpl_minizip_unzip.h	??
cpl_minizip_zip.h	??
cpl_multiproc.h	??
cpl_odbc.h	149
cpl_port.h	149
cpl_quad_tree.h	150
cpl_string.h	152
cpl_time.h	??
cpl_vsi.h	164
cpl_vsi_virtual.h	??
cpl_win32ce_api.h	??
cpl_wince.h	??
cplkeywordparser.h	??
gdal_csv.h	??
iso8211.h	??
sdts_al.h	??
sdtsdataset.cpp	176

Chapter 9

Class Documentation

9.1 _CPLHashSet Struct Reference

The documentation for this struct was generated from the following file:

- [cpl_hash_set.cpp](#)

9.2 _CPLList Struct Reference

```
#include <cpl_list.h>
```

Public Attributes

- `void * pData`
- `struct _CPLList * psNext`

9.2.1 Detailed Description

List element structure.

9.2.2 Member Data Documentation

9.2.2.1 `void* _CPLList::pData`

Pointer to the data object. Should be allocated and freed by the caller.

9.2.2.2 `struct _CPLList* _CPLList::psNext`

Pointer to the next element in list. NULL, if current element is the last one

The documentation for this struct was generated from the following file:

- [cpl_list.h](#)

9.3 _CPLQuadTree Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_quad_tree.cpp`

9.4 _QuadTreeNode Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_quad_tree.cpp`

9.5 CPLErrorContext Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_error.cpp`

9.6 CPLHTTPResult Struct Reference

```
#include <cpl_http.h>
```

Public Attributes

- int `nStatus`
- char * `pszContentType`
- char * `pszErrBuf`
- int `nDataLen`
- GByte * `pabyData`
- char ** `papszHeaders`
- int `nMimePartCount`
- `CPLMimePart` * `pasMimePart`

9.6.1 Detailed Description

Describe the result of a `CPLHTTPFetch()` call

9.6.2 Member Data Documentation

9.6.2.1 int CPLHTTPResult::nDataLen

Length of the `pabyData` buffer

9.6.2.2 int CPLHTTPResult::nMimePartCount

Number of parts in a multipart message

9.6.2.3 int CPLHTTPResult::nStatus

cURL error code : 0=success, non-zero if request failed

9.6.2.4 GByte* CPLHTTPResult::pabyData

Buffer with downloaded data

9.6.2.5 char CPLHTTPResult::papszHeaders**

Headers returned

9.6.2.6 CPLMimePart* CPLHTTPResult::pasMimePart

Array of parts (resolved by [CPLHTTPParseMultipartMime\(\)](#))

9.6.2.7 char* CPLHTTPResult::pszContentType

Content-Type of the response

9.6.2.8 char* CPLHTTPResult::pszErrBuf

Error message from curl, or NULL

The documentation for this struct was generated from the following file:

- [cpl_http.h](#)

9.7 CPLKeywordParser Class Reference

The documentation for this class was generated from the following files:

- [cplkeywordparser.h](#)
- [cplkeywordparser.cpp](#)

9.8 CPLMimePart Struct Reference

```
#include <cpl_http.h>
```

Public Attributes

- [char ** papszHeaders](#)
- [GByte * pabyData](#)
- [int nDataLen](#)

9.8.1 Detailed Description

Describe a part of a multipart message

9.8.2 Member Data Documentation

9.8.2.1 int CPLMimePart::nDataLen

Buffer length

9.8.2.2 GByte* CPLMimePart::pabyData

Buffer with data of the part

9.8.2.3 char** CPLMimePart::papszHeaders

NULL terminated array of headers

The documentation for this struct was generated from the following file:

- [cpl_http.h](#)

9.9 CPLODBCDriverInstaller Class Reference

```
#include <cpl_odbc.h>
```

Public Member Functions

- int [InstallDriver](#) (const char *pszDriver, const char *pszPathIn, WORD fRequest=ODBC_INSTALL_COMPLETE)
- int [RemoveDriver](#) (const char *pszDriverName, int fRemoveDSN=FALSE)

9.9.1 Detailed Description

A class providing functions to install or remove ODBC driver.

9.9.2 Member Function Documentation

9.9.2.1 int CPLODBCDriverInstaller::InstallDriver (const char * *pszDriver*, const char * *pszPathIn*, WORD *fRequest* = ODBC_INSTALL_COMPLETE)

Installs ODBC driver or updates definition of already installed driver. Internally, it calls ODBC's SQLInstallDriverEx function.

Parameters

<i>pszDriver</i>	- The driver definition as a list of keyword-value pairs describing the driver (See ODBC API Reference).
<i>pszPathIn</i>	- Full path of the target directory of the installation, or a null pointer (for unixODBC, NULL is passed).
<i>fRequest</i>	- The <i>fRequest</i> argument must contain one of the following values: ODBC_INSTALL_COMPLETE - (default) complete the installation request ODBC_INSTALL_INQUIRY - inquire about where a driver can be installed

Returns

TRUE indicates success, FALSE if it fails.

9.9.2.2 int CPLODBCDriverInstaller::RemoveDriver (const char * *pszDriverName*, int *fRemoveDSN* = FALSE)

Removes or changes information about the driver from the Odbcinst.ini entry in the system information.

Parameters

<i>pszDriverName</i>	- The name of the driver as registered in the Odbcinst.ini key of the system information.
<i>fRemoveDSN</i>	- TRUE: Remove DSNs associated with the driver specified in <i>pszDriver</i> . FALSE: Do not remove DSNs associated with the driver specified in <i>pszDriver</i> .

Returns

The function returns TRUE if it is successful, FALSE if it fails. If no entry exists in the system information when this function is called, the function returns FALSE. In order to obtain usage count value, call GetUsageCount().

The documentation for this class was generated from the following files:

- [cpl_odb.h](#)
- [cpl_odb.cpp](#)

9.10 CPLODBCSession Class Reference

```
#include <cpl_odb.h>
```

Public Member Functions

- int [EstablishSession](#) (const char **pszDSN*, const char **pszUserId*, const char **pszPassword*)
- const char * [GetLastError](#) ()

9.10.1 Detailed Description

A class representing an ODBC database session.

Includes error collection services.

9.10.2 Member Function Documentation

9.10.2.1 int CPLODBCSession::EstablishSession (const char * *pszDSN*, const char * *pszUserId*, const char * *pszPassword*)

Connect to database and logon.

Parameters

<i>pszDSN</i>	The name of the DSN being used to connect. This is not optional.
<i>pszUserId</i>	the userid to logon as, may be NULL if not required, or provided by the DSN.
<i>pszPassword</i>	the password to logon with. May be NULL if not required or provided by the DSN.

Returns

TRUE on success or FALSE on failure. Call [GetLastError\(\)](#) to get details on failure.

9.10.2.2 const char * CPLODBCSession::GetLastError ()

Returns the last ODBC error message.

Returns

pointer to an internal buffer with the error message in it. Do not free or alter. Will be an empty (but not NULL) string if there is no pending error info.

The documentation for this class was generated from the following files:

- [cpl_odbc.h](#)
- [cpl_odbc.cpp](#)

9.11 CPLODBCStatement Class Reference

```
#include <cpl_odbc.h>
```

Public Member Functions

- void [Clear \(\)](#)
- void [AppendEscaped \(const char *\)](#)
- void [Append \(const char *\)](#)
- void [Append \(int\)](#)
- void [Append \(double\)](#)
- int [Appendf \(const char *,...\) CPL_PRINT_FUNC_FORMAT\(2](#)
- int [ExecuteSQL \(const char *=NULL\)](#)
- int [Fetch \(int nOrientation=SQL_FETCH_NEXT, int nOffset=0\)](#)
- int [GetColCount \(\)](#)
- const char * [GetColName \(int\)](#)
- short [GetColType \(int\)](#)
- const char * [GetColTypeName \(int\)](#)
- short [GetColSize \(int\)](#)
- short [GetColPrecision \(int\)](#)
- short [GetColNullable \(int\)](#)
- int [GetColId \(const char *\)](#)
- const char * [GetColData \(int, const char *=NULL\)](#)
- const char * [GetColData \(const char *, const char *=NULL\)](#)
- int [GetColumns \(const char *pszTable, const char *pszCatalog=NULL, const char *pszSchema=NULL\)](#)
- int [GetPrimaryKeys \(const char *pszTable, const char *pszCatalog=NULL, const char *pszSchema=NULL\)](#)
- int [GetTables \(const char *pszCatalog=NULL, const char *pszSchema=NULL\)](#)
- void [DumpResult \(FILE *fp, int bShowSchema=FALSE\)](#)

Static Public Member Functions

- static CPLString [GetTypeNames \(int\)](#)
- static SQLSMALLINT [GetTypeMapping \(SQLSMALLINT\)](#)

9.11.1 Detailed Description

Abstraction for statement, and resultset.

Includes methods for executing an SQL statement, and for accessing the resultset from that statement. Also provides for executing other ODBC requests that produce results sets such as SQLColumns() and SQLTables() requests.

9.11.2 Member Function Documentation

9.11.2.1 void CPLODBCStatement::Append (const char * *pszText*)

Append text to internal command.

The passed text is appended to the internal SQL command text.

Parameters

<i>pszText</i>	text to append.
----------------	-----------------

9.11.2.2 void CPLODBCStatement::Append (int *nValue*)

Append to internal command.

The passed value is formatted and appended to the internal SQL command text.

Parameters

<i>nValue</i>	value to append to the command.
---------------	---------------------------------

9.11.2.3 void CPLODBCStatement::Append (double *dfValue*)

Append to internal command.

The passed value is formatted and appended to the internal SQL command text.

Parameters

<i>dfValue</i>	value to append to the command.
----------------	---------------------------------

9.11.2.4 void CPLODBCStatement::AppendEscaped (const char * *pszText*)

Append text to internal command.

The passed text is appended to the internal SQL command text after escaping any special characters so it can be used as a character string in an SQL statement.

Parameters

<i>pszText</i>	text to append.
----------------	-----------------

9.11.2.5 int CPLODBCStatement::Appendf (const char * *pszFormat*, ...)

Append to internal command.

The passed format is used to format other arguments and the result is appended to the internal command text.

Long results may not be formatted properly, and should be appended with the direct [Append\(\)](#) methods.

Parameters

<i>pszFormat</i>	printf() style format string.
------------------	-------------------------------

Returns

FALSE if formatting fails due to result being too large.

9.11.2.6 void CPLODBCStatement::Clear()

Clear internal command text and result set definitions.

9.11.2.7 void CPLODBCStatement::DumpResult(FILE * *fp*, int *bShowSchema* = FALSE)

Dump resultset to file.

The contents of the current resultset are dumped in a simply formatted form to the provided file. If requested, the schema definition will be written first.

Parameters

<i>fp</i>	the file to write to. stdout or stderr are acceptable.
<i>bShowSchema</i>	TRUE to force writing schema information for the rowset before the rowset data itself. Default is FALSE.

9.11.2.8 int CPLODBCStatement::ExecuteSQL(const char * *pszStatement* = NULL)

Execute an SQL statement.

This method will execute the passed (or stored) SQL statement, and initialize information about the resultset if there is one. If a NULL statement is passed, the internal stored statement that has been previously set via [Append\(\)](#) or [Appendf\(\)](#) calls will be used.

Parameters

<i>pszStatement</i>	the SQL statement to execute, or NULL if the internally saved one should be used.
---------------------	---

Returns

TRUE on success or FALSE if there is an error. Error details can be fetched with OGRODBCSession::GetLastError().

9.11.2.9 int CPLODBCStatement::Fetch(int *nOrientation* = SQL_FETCH_NEXT, int *nOffset* = 0)

Fetch a new record.

Requests the next row in the current resultset using the SQLFetchScroll() call. Note that many ODBC drivers only support the default forward fetching one record at a time. Only SQL_FETCH_NEXT (the default) should be considered reliable on all drivers.

Currently it isn't clear how to determine whether an error or a normal out of data condition has occurred if [Fetch\(\)](#) fails.

Parameters

<i>nOrientation</i>	One of SQL_FETCH_NEXT, SQL_FETCH_LAST, SQL_FETCH_PRIOR, SQL_FETCH_ABSOLUTE, or SQL_FETCH_RELATIVE (default is SQL_FETCH_NEXT).
<i>nOffset</i>	the offset (number of records), ignored for some orientations.

Returns

TRUE if a new row is successfully fetched, or FALSE if not.

9.11.2.10 int CPLODBCStatement::GetColCount ()

Fetch the resultset column count.

Returns

the column count, or zero if there is no resultset.

9.11.2.11 const char * CPLODBCStatement::GetColData (int *iCol*, const char * *pszDefault* = NULL)

Fetch column data.

Fetches the data contents of the requested column for the currently loaded row. The result is returned as a string regardless of the column type. NULL is returned if an illegal column is given, or if the actual column is "NULL".

Parameters

<i>iCol</i>	the zero based column to fetch.
<i>pszDefault</i>	the value to return if the column does not exist, or is NULL. Defaults to NULL.

Returns

pointer to internal column data or NULL on failure.

9.11.2.12 const char * CPLODBCStatement::GetColData (const char * *pszColName*, const char * *pszDefault* = NULL)

Fetch column data.

Fetches the data contents of the requested column for the currently loaded row. The result is returned as a string regardless of the column type. NULL is returned if an illegal column is given, or if the actual column is "NULL".

Parameters

<i>pszColName</i>	the name of the column requested.
<i>pszDefault</i>	the value to return if the column does not exist, or is NULL. Defaults to NULL.

Returns

pointer to internal column data or NULL on failure.

9.11.2.13 int CPLODBCStatement::GetColId (const char * *pszColName*)

Fetch column index.

Gets the column index corresponding with the passed name. The name comparisons are case insensitive.

Parameters

<i>pszColName</i>	the name to search for.
-------------------	-------------------------

Returns

the column index, or -1 if not found.

9.11.2.14 const char * CPLODBCStatement::GetColName (int *iCol*)

Fetch a column name.

Parameters

<i>iCol</i>	the zero based column index.
-------------	------------------------------

Returns

NULL on failure (out of bounds column), or a pointer to an internal copy of the column name.

9.11.2.15 short CPLODBCStatement::GetColNullable (int *iCol*)

Fetch the column nullability.

Parameters

<i>iCol</i>	the zero based column index.
-------------	------------------------------

Returns

TRUE if the column may contains or FALSE otherwise.

9.11.2.16 short CPLODBCStatement::GetColPrecision (int *iCol*)

Fetch the column precision.

Parameters

<i>iCol</i>	the zero based column index.
-------------	------------------------------

Returns

column precision, may be zero or the same as column size for columns to which it does not apply.

9.11.2.17 short CPLODBCStatement::GetColSize (int *iCol*)

Fetch the column width.

Parameters

<i>iCol</i>	the zero based column index.
-------------	------------------------------

Returns

column width, zero for unknown width columns.

9.11.2.18 short CPLODBCStatement::GetColType (int *iCol*)

Fetch a column data type.

The return type code is a an ODBC SQL_ code, one of SQL_UNKNOWN_TYPE, SQL_CHAR, SQL_NUMERIC, SQL_DECIMAL, SQL_INTEGER, SQL_SMALLINT, SQL_FLOAT, SQL_REAL, SQL_DOUBLE, SQL_DATETIME, SQL_VARCHAR, SQL_TYPE_DATE, SQL_TYPE_TIME, SQL_TYPE_TIMESTAMP.

Parameters

<i>iCol</i>	the zero based column index.
-------------	------------------------------

Returns

type code or -1 if the column is illegal.

9.11.2.19 const char * CPLODBCStatement::GetColTypeName (int *iCol*)

Fetch a column data type name.

Returns data source-dependent data type name; for example, "CHAR", "VARCHAR", "MONEY", "LONG VARBIN-AR", or "CHAR () FOR BIT DATA".

Parameters

<i>iCol</i>	the zero based column index.
-------------	------------------------------

Returns

NULL on failure (out of bounds column), or a pointer to an internal copy of the column dat type name.

9.11.2.20 int CPLODBCStatement::GetColumns (const char * *pszTable*, const char * *pszCatalog* = NULL, const char * *pszSchema* = NULL)

Fetch column definitions for a table.

The SQLColumn() method is used to fetch the definitions for the columns of a table (or other queriable object such as a view). The column definitions are digested and used to populate the [CPLODBCStatement](#) column definitions essentially as if a "SELECT * FROM tablename" had been done; however, no resultset will be available.

Parameters

<i>pszTable</i>	the name of the table to query information on. This should not be empty.
<i>pszCatalog</i>	the catalog to find the table in, use NULL (the default) if no catalog is available.
<i>pszSchema</i>	the schema to find the table in, use NULL (the default) if no schema is available.

Returns

TRUE on success or FALSE on failure.

9.11.2.21 int CPLODBCStatement::GetPrimaryKeys (const char * *pszTable*, const char * *pszCatalog* = NULL, const char * *pszSchema* = NULL)

Fetch primary keys for a table.

The SQLPrimaryKeys() function is used to fetch a list of fields forming the primary key. The result is returned as a result set matching the SQLPrimaryKeys() function result set. The 4th column in the result set is the column name of the key, and if the result set contains only one record then that single field will be the complete primary key.

Parameters

<i>pszTable</i>	the name of the table to query information on. This should not be empty.
<i>pszCatalog</i>	the catalog to find the table in, use NULL (the default) if no catalog is available.
<i>pszSchema</i>	the schema to find the table in, use NULL (the default) if no schema is available.

Returns

TRUE on success or FALSE on failure.

9.11.2.22 int CPLODBCStatement::GetTables (const char * *pszCatalog* = NULL, const char * *pszSchema* = NULL)

Fetch tables in database.

The SQLTables() function is used to fetch a list tables in the database. The result is returned as a result set matching the SQLTables() function result set. The 3rd column in the result set is the table name. Only tables of type "TABLE" are returned.

Parameters

<i>pszCatalog</i>	the catalog to find the table in, use NULL (the default) if no catalog is available.
<i>pszSchema</i>	the schema to find the table in, use NULL (the default) if no schema is available.

Returns

TRUE on success or FALSE on failure.

9.11.2.23 SQLSMALLINT CPLODBCStatement::GetTypeMapping (SQLSMALLINT *nTypeCode*) [static]

Get appropriate C data type for SQL column type.

Returns a C data type code, corresponding to the indicated SQL data type code (as returned from [CPLODBCStatement::GetColType\(\)](#)).

Parameters

<i>nTypeCode</i>	the SQL_ code, such as SQL_CHAR.
------------------	----------------------------------

Returns

data type code. The valid code is always returned. If SQL code is not recognised, SQL_C_BINARY will be returned.

9.11.2.24 CPLString CPLODBCStatement::GetTypeName (int *nTypeCode*) [static]

Get name for SQL column type.

Returns a string name for the indicated type code (as returned from [CPLODBCStatement::GetColType\(\)](#)).

Parameters

<code>nTypeCode</code>	the SQL_ code, such as SQL_CHAR.
------------------------	----------------------------------

Returns

internal string, "UNKNOWN" if code not recognised.

The documentation for this class was generated from the following files:

- [cpl_odbc.h](#)
- [cpl_odbc.cpp](#)

9.12 CPLRectObj Struct Reference

The documentation for this struct was generated from the following file:

- [cpl_quad_tree.h](#)

9.13 CPLSharedFileInfo Struct Reference

The documentation for this struct was generated from the following file:

- [cpl_conv.h](#)

9.14 CPLStdCallThreadInfo Struct Reference

The documentation for this struct was generated from the following file:

- [cpl_multiproc.cpp](#)

9.15 CPLXMLNode Struct Reference

```
#include <cpl_minixml.h>
```

Public Attributes

- **CPLXMLNodeType eType**
Node type.
- **char * pszValue**
Node value.
- **struct CPLXMLNode * psNext**
Next sibling.
- **struct CPLXMLNode * psChild**
Child node.

9.15.1 Detailed Description

Document node structure.

This C structure is used to hold a single text fragment representing a component of the document when parsed. It should be allocated with the appropriate CPL function, and freed with [CPLDestroyXMLNode\(\)](#). The structure contents should not normally be altered by application code, but may be freely examined by application code.

Using the psChild and psNext pointers, a hierarchical tree structure for a document can be represented as a tree of [CPLXMLNode](#) structures.

9.15.2 Member Data Documentation

9.15.2.1 `CPLXMLNodeType CPLXMLNode::eType`

Node type.

One of CXT_Element, CXT_Text, CXT_Attribute, CXT_Comment, or CXT_Literal.

9.15.2.2 `struct CPLXMLNode* CPLXMLNode::psChild`

Child node.

Pointer to first child node, if any. Only CXT_Element and CXT_Attribute nodes should have children. For CXT_Attribute it should be a single CXT_Text value node, while CXT_Element can have any kind of child. The full list of children for a node are identified by walking the psNext's starting with the psChild node.

9.15.2.3 `struct CPLXMLNode* CPLXMLNode::psNext`

Next sibling.

Pointer to next sibling, that is the next node appearing after this one that has the same parent as this node. NULL if this node is the last child of the parent element.

9.15.2.4 `char* CPLXMLNode::pszValue`

Node value.

For CXT_Element this is the name of the element, without the angle brackets. Note there is a single CXT_Element even when the document contains a start and end element tag. The node represents the pair. All text or other elements between the start and end tag will appear as children nodes of this CXT_Element node.

For CXT_Attribute the pszValue is the attribute name. The value of the attribute will be a CXT_Text child.

For CXT_Text this is the text itself (value of an attribute, or a text fragment between an element start and end tags).

For CXT_Literal it is all the literal text. Currently this is just used for !DOCTYPE lines, and the value would be the entire line.

For CXT_Comment the value is all the literal text within the comment, but not including the comment start/end indicators ("<–" and "–>").

The documentation for this struct was generated from the following file:

- [cpl_minixml.h](#)

9.16 ctb Struct Reference

The documentation for this struct was generated from the following file:

- cpl_csv.cpp

9.17 curfile_info Struct Reference

The documentation for this struct was generated from the following file:

- cpl_minizip_zip.cpp

9.18 DDFField Class Reference

```
#include <iso8211.h>
```

Public Member Functions

- void [Dump](#) (FILE *fp)
- const char * [GetSubfieldData](#) (DDFSUBFIELDDEFN *, int *=NULL, int=0)
- const char * [GetInstanceData](#) (int nInstance, int *pnSize)
- const char * [GetData](#) ()
- int [GetDataSize](#) ()
- int [GetRepeatCount](#) ()
- DDFFIELDDEFN * [GetFieldDefn](#) ()

9.18.1 Detailed Description

This object represents one field in a [DDFRecord](#). This models an instance of the fields data, rather than it's data definition which is handled by the [DDFFieldDefn](#) class. Note that a [DDFField](#) doesn't have DDFSubfield children as you would expect. To extract subfield values use [GetSubfieldData\(\)](#) to find the right data pointer and then use [ExtractIntData\(\)](#), [ExtractFloatData\(\)](#) or [ExtractStringData\(\)](#).

9.18.2 Member Function Documentation

9.18.2.1 void DDFField::Dump (FILE * fp)

Write out field contents to debugging file.

A variety of information about this field, and all it's subfields is written to the given debugging file handle. Note that field definition information (ala [DDFFieldDefn](#)) isn't written.

Parameters

<i>fp</i>	The standard io file handle to write to. ie. stderr
-----------	---

9.18.2.2 const char* DDFField::GetData () [inline]

Return the pointer to the entire data block for this record. This is an internal copy, and shouldn't be freed by the application.

9.18.2.3 int DDFField::GetDataSize () [inline]

Return the number of bytes in the data block returned by [GetData\(\)](#).

9.18.2.4 `DDFFieldDefn* DDFField::GetFieldDefn() [inline]`

Fetch the corresponding `DDFFieldDefn`.

9.18.2.5 `const char * DDFField::GetInstanceData(int nInstance, int * pnInstanceSize)`

Get field instance data and size.

The returned data pointer and size values are suitable for use with `DDFRecord::SetFieldRaw()`.

Parameters

<code>nInstance</code>	a value from 0 to <code>GetRepeatCount()</code> -1.
<code>pnInstanceSize</code>	a location to put the size (in bytes) of the field instance data returned. This size will include the unit terminator (if any), but not the field terminator. This size pointer may be NULL if not needed.

Returns

the data pointer, or NULL on error.

9.18.2.6 `int DDFField::GetRepeatCount()`

How many times do the subfields of this record repeat? This will always be one for non-repeating fields.

Returns

The number of times that the subfields of this record occur in this record. This will be one for non-repeating fields.

See Also

`8211view example program` for demonstration of handling repeated fields properly.

9.18.2.7 `const char * DDFField::GetSubfieldData(DDFSubfieldDefn * poSFDefn, int * pnMaxBytes = NULL, int iSubfieldIndex = 0)`

Fetch raw data pointer for a particular subfield of this field.

The passed `DDFSubfieldDefn` (`poSFDefn`) should be acquired from the `DDFFieldDefn` corresponding with this field. This is normally done once before reading any records. This method involves a series of calls to `DDFSubfield::GetDataLength()` in order to track through the `DDFField` data to that belonging to the requested subfield. This can be relatively expensive.

Parameters

<code>poSFDefn</code>	The definition of the subfield for which the raw data pointer is desired.
<code>pnMaxBytes</code>	The maximum number of bytes that can be accessed from the returned data pointer is placed in this int, unless it is NULL.
<code>iSubfieldIndex</code>	The instance of this subfield to fetch. Use zero (the default) for the first instance.

Returns

A pointer into the [DDFField](#)'s data that belongs to the subfield. This returned pointer is invalidated by the next record read ([DDFRecord::ReadRecord\(\)](#)) and the returned pointer should not be freed by the application.

The documentation for this class was generated from the following files:

- [iso8211.h](#)
- [ddffield.cpp](#)

9.19 DDFFieldDefn Class Reference

```
#include <iso8211.h>
```

Public Member Functions

- void [Dump](#) (FILE *fp)
- const char * [GetName](#) ()
- const char * [GetDescription](#) ()
- int [GetSubfieldCount](#) ()
- [DDFSubfieldDefn](#) * [GetSubfield](#) (int i)
- [DDFSubfieldDefn](#) * [FindSubfieldDefn](#) (const char *)
- int [GetFixedWidth](#) ()
- int [IsRepeating](#) ()
- void [SetRepeatingFlag](#) (int n)
- char * [GetDefaultValue](#) (int *pnSize)

9.19.1 Detailed Description

Information from the DDR defining one field. Note that just because a field is defined for a [DDFModule](#) doesn't mean that it actually occurs on any records in the module. DDFFieldDefns are normally just significant as containers of the DDFSubfieldDefns.

9.19.2 Member Function Documentation

9.19.2.1 void DDFFieldDefn::Dump (FILE * fp)

Write out field definition info to debugging file.

A variety of information about this field definition, and all it's subfields is written to the give debugging file handle.

Parameters

<i>fp</i>	The standard io file handle to write to. ie. stderr
-----------	---

9.19.2.2 DDFSubfieldDefn * DDFFieldDefn::FindSubfieldDefn (const char * pszMnemonic)

Find a subfield definition by it's mnemonic tag.

Parameters

<i>pszMnemonic</i>	The name of the field.
--------------------	------------------------

Returns

The subfield pointer, or NULL if there isn't any such subfield.

9.19.2.3 `char * DDFFieldDefn::GetDefaultValue(int * pnSize)`

Return default data for field instance.

9.19.2.4 `const char* DDFFieldDefn::GetDescription() [inline]`

Fetch a longer descriptio of this field.

Returns

this is an internal copy and shouldn't be freed.

9.19.2.5 `int DDFFieldDefn::GetWidth() [inline]`

Get the width of this field. This function isn't normally used by applications.

Returns

The width of the field in bytes, or zero if the field is not apparently of a fixed width.

9.19.2.6 `const char* DDFFieldDefn::GetName() [inline]`

Fetch a pointer to the field name (tag).

Returns

this is an internal copy and shouldn't be freed.

9.19.2.7 `DDFSubfieldDefn * DDFFieldDefn::GetSubfield(int i)`

Fetch a subfield by index.

Parameters

<code>i</code>	The index subfield index. (Between 0 and GetSubfieldCount() -1)
----------------	---

Returns

The subfield pointer, or NULL if the index is out of range.

9.19.2.8 `int DDFFieldDefn::GetSubfieldCount() [inline]`

Get the number of subfields.

9.19.2.9 `int DDFFieldDefn::IsRepeating() [inline]`

Fetch repeating flag.

See Also[DDFField::GetRepeatCount\(\)](#)**Returns**

TRUE if the field is marked as repeating.

9.19.2.10 void DDFFieldDefn::SetRepeatingFlag (int n) [inline]

this is just for an S-57 hack for swedish data

The documentation for this class was generated from the following files:

- [iso8211.h](#)
- [ddffielddefn.cpp](#)

9.20 DDFModule Class Reference

```
#include <iso8211.h>
```

Public Member Functions

- [DDFModule \(\)](#)
- [~DDFModule \(\)](#)
- [int Open \(const char *pszFilename, int bFailQuietly=FALSE\)](#)
- [void Close \(\)](#)
- [void Dump \(FILE *fp\)](#)
- [DDFRecord * ReadRecord \(void\)](#)
- [void Rewind \(long nOffset=-1\)](#)
- [DDFFieldDefn * FindFieldDefn \(const char *\)](#)
- [int GetFieldCount \(\)](#)
- [DDFFieldDefn * GetField \(int\)](#)
- [void AddField \(DDFFieldDefn *poNewFDefn\)](#)

9.20.1 Detailed Description

The primary class for reading ISO 8211 files. This class contains all the information read from the DDR record, and is used to read records from the file.

9.20.2 Constructor & Destructor Documentation

9.20.2.1 DDFModule::DDFModule ()

The constructor.

9.20.2.2 DDFModule::~DDFModule ()

The destructor.

9.20.3 Member Function Documentation

9.20.3.1 void DDFModule::AddField (DDFFieldDefn * *poNewFDefn*)

Add new field definition.

Field definitions may only be added to DDFModules being used for writing, not those being used for reading. Ownership of the [DDFFieldDefn](#) object is taken by the [DDFModule](#).

Parameters

<i>poNewFDefn</i>	definition to be added to the module.
-------------------	---------------------------------------

9.20.3.2 void DDFModule::Close ()

Close an ISO 8211 file.

9.20.3.3 void DDFModule::Dump (FILE * *fp*)

Write out module info to debugging file.

A variety of information about the module is written to the debugging file. This includes all the field and subfield definitions read from the header.

Parameters

<i>fp</i>	The standard io file handle to write to. ie. stderr.
-----------	--

9.20.3.4 DDFFieldDefn * DDFModule::FindFieldDefn (const char * *pszFieldName*)

Fetch the definition of the named field.

This function will scan the [DDFFieldDefn](#)'s on this module, to find one with the indicated field name.

Parameters

<i>pszFieldName</i>	The name of the field to search for. The comparison is case insensitive.
---------------------	--

Returns

A pointer to the request [DDFFieldDefn](#) object is returned, or NULL if none matching the name are found. The return object remains owned by the [DDFModule](#), and should not be deleted by application code.

9.20.3.5 DDFFieldDefn * DDFModule::GetField (int *i*)

Fetch a field definition by index.

Parameters

<i>i</i>	(from 0 to GetFieldCount() - 1.
----------	---

Returns

the returned field pointer or NULL if the index is out of range.

9.20.3.6 int DDFModule::GetFieldCount() [inline]

Fetch the number of defined fields.

9.20.3.7 int DDFModule::Open (const char * *pszFilename*, int *bFailQuietly* = FALSE)

Open a ISO 8211 (DDF) file for reading.

If the open succeeds the data descriptive record (DDR) will have been read, and all the field and subfield definitions will be available.

Parameters

<i>pszFilename</i>	The name of the file to open.
<i>bFailQuietly</i>	If FALSE a CPL Error is issued for non-8211 files, otherwise quietly return NULL.

Returns

FALSE if the open fails or TRUE if it succeeds. Errors messages are issued internally with CPLError().

9.20.3.8 DDFRecord * DDFModule::ReadRecord (void)

Read one record from the file.

Returns

A pointer to a [DDFRecord](#) object is returned, or NULL if a read error, or end of file occurs. The returned record is owned by the module, and should not be deleted by the application. The record is only valid until the next [ReadRecord\(\)](#) at which point it is overwritten.

9.20.3.9 void DDFModule::Rewind (long *nOffset* = -1)

Return to first record.

The next call to [ReadRecord\(\)](#) will read the first data record in the file.

Parameters

<i>nOffset</i>	the offset in the file to return to. By default this is -1, a special value indicating that reading should return to the first data record. Otherwise it is an absolute byte offset in the file.
----------------	--

The documentation for this class was generated from the following files:

- iso8211.h
- ddfmodule.cpp

9.21 DDFRecord Class Reference

```
#include <iso8211.h>
```

Public Member Functions

- [DDFRecord * Clone \(\)](#)
- [DDFRecord * CloneOn \(DDFModule *\)](#)

- void [Dump](#) (FILE *)
- int [GetFieldCount](#) ()
- [DDFField](#) * [FindField](#) (const char *, int=0)
- [DDFField](#) * [GetField](#) (int)
- int [GetIntSubfield](#) (const char *, int, const char *, int, int *=NULL)
- double [GetFloatSubfield](#) (const char *, int, const char *, int, int *=NULL)
- const char * [GetStringSubfield](#) (const char *, int, const char *, int, int *=NULL)
- int [SetIntSubfield](#) (const char *pszField, int iFieldIndex, const char *pszSubfield, int iSubfieldIndex, int nValue)
- int [SetStringSubfield](#) (const char *pszField, int iFieldIndex, const char *pszSubfield, int iSubfieldIndex, const char *pszValue, int nValueLength=-1)
- int [SetFloatSubfield](#) (const char *pszField, int iFieldIndex, const char *pszSubfield, int iSubfieldIndex, double dfNewValue)
- int [GetDataSize](#) ()
- const char * [GetData](#) ()
- [DDFModule](#) * [GetModule](#) ()
- int [ResizeField](#) ([DDFField](#) *poField, int nNewDataSize)
- int [DeleteField](#) ([DDFField](#) *poField)
- [DDFField](#) * [AddField](#) ([DDFFieldDefn](#) *)
- int [CreateDefaultFieldInstance](#) ([DDFField](#) *poField, int iIndexWithinField)
- int [SetFieldRaw](#) ([DDFField](#) *poField, int iIndexWithinField, const char *pachRawData, int nRawDataSize)
- int [Write](#) ()

9.21.1 Detailed Description

Contains instance data from one data record (DR). The data is contained as a list of [DDFField](#) instances partitioning the raw data into fields.

9.21.2 Member Function Documentation

9.21.2.1 [DDFField](#) * [DDFRecord::AddField](#) ([DDFFieldDefn](#) * *poDefn*)

Add a new field to record.

Add a new zero sized field to the record. The new field is always added at the end of the record.

NOTE: This method doesn't currently update the header information for the record to include the field information for this field, so the resulting record image isn't suitable for writing to disk. However, everything else about the record state should be updated properly to reflect the new field.

Parameters

<i>poDefn</i>	the definition of the field to be added.
---------------	--

Returns

the field object on success, or NULL on failure.

9.21.2.2 [DDFRecord](#) * [DDFRecord::Clone](#) ()

Make a copy of a record.

This method is used to make a copy of a record that will become (mostly) the property of application. However, it is automatically destroyed if the [DDFModule](#) it was created relative to is destroyed, as its field and subfield definitions relate to that [DDFModule](#). However, it does persist even when the record returned by [DDFModule::ReadRecord\(\)](#) is invalidated, such as when reading a new record. This allows an application to cache whole DDFRecords.

Returns

A new copy of the [DDFRecord](#). This can be deleted by the application when no longer needed, otherwise it will be cleaned up when the [DDFModule](#) it relates to is destroyed or closed.

9.21.2.3 DDFRecord * DDFRecord::CloneOn (DDFModule * *poTargetModule*)

Recreate a record referencing another module.

Works similarly to the [DDFRecord::Clone\(\)](#) method, but creates the new record with reference to a different [DDFModule](#). All [DDFFieldDefn](#) references are transcribed onto the new module based on field names. If any fields don't have a similarly named field on the target module the operation will fail. No validation of field types and properties is done, but this operation is intended only to be used between modules with matching definitions of all affected fields.

The new record will be managed as a clone by the target module in a manner similar to regular clones.

Parameters

<i>poTargetModule</i>	the module on which the record copy should be created.
-----------------------	--

Returns

NULL on failure or a pointer to the cloned record.

9.21.2.4 int DDFRecord::CreateDefaultFieldInstance (DDFField * *poField*, int *iIndexWithinField*)

Initialize default instance.

This method is normally only used internally by the [AddField\(\)](#) method to initialize the new field instance with default subfield values. It installs default data for one instance of the field in the record using the [DDFFieldDefn::GetDefaultValue\(\)](#) method and [DDFRecord::SetFieldRaw\(\)](#).

Parameters

<i>poField</i>	the field within the record to be assign a default instance.
<i>iIndexWithinField</i>	the instance to set (may not have been tested with values other than 0).

Returns

TRUE on success or FALSE on failure.

9.21.2.5 int DDFRecord::DeleteField (DDFField * *poTarget*)

Delete a field instance from a record.

Remove a field from this record, cleaning up the data portion and repacking the fields list. We don't try to reallocate the data area of the record to be smaller.

NOTE: This method doesn't actually remove the header information for this field from the record tag list yet. This should be added if the resulting record is even to be written back to disk!

Parameters

<i>poTarget</i>	the field instance on this record to delete.
-----------------	--

Returns

TRUE on success, or FALSE on failure. Failure can occur if poTarget isn't really a field on this record.

9.21.2.6 void DDFRecord::Dump (FILE * fp)

Write out record contents to debugging file.

A variety of information about this record, and all it's fields and subfields is written to the given debugging file handle. Note that field definition information (ala [DDFFieldDefn](#)) isn't written.

Parameters

<i>fp</i>	The standard io file handle to write to. ie. stderr
-----------	---

9.21.2.7 DDFField * DDFRecord::FindField (const char * pszName, int iFieldIndex = 0)

Find the named field within this record.

Parameters

<i>pszName</i>	The name of the field to fetch. The comparison is case insensitive.
<i>iFieldIndex</i>	The instance of this field to fetch. Use zero (the default) for the first instance.

Returns

Pointer to the requested [DDFField](#). This pointer is to an internal object, and should not be freed. It remains valid until the next record read.

9.21.2.8 const char* DDFRecord::GetData () [inline]

Fetch the raw data for this record. The returned pointer is effectively to the data for the first field of the record, and is of size [GetDataSize\(\)](#).

9.21.2.9 int DDFRecord::GetDataSize () [inline]

Fetch size of records raw data ([GetData\(\)](#)) in bytes.

9.21.2.10 DDFField * DDFRecord::GetField (int i)

Fetch field object based on index.

Parameters

<i>i</i>	The index of the field to fetch. Between 0 and GetFieldCount() -1.
----------	--

Returns

A [DDFField](#) pointer, or NULL if the index is out of range.

9.21.2.11 int DDFRecord::GetFieldCount () [inline]

Get the number of DDFFields on this record.

9.21.2.12 double DDFRecord::GetFloatSubfield (const char * *pszField*, int *iFieldIndex*, const char * *pszSubfield*, int *iSubfieldIndex*, int * *pnSuccess* = NULL)

Fetch value of a subfield as a float (double). This is a convenience function for fetching a subfield of a field within this record.

Parameters

<i>pszField</i>	The name of the field containing the subfield.
<i>iFieldIndex</i>	The instance of this field within the record. Use zero for the first instance of this field.
<i>pszSubfield</i>	The name of the subfield within the selected field.
<i>iSubfieldIndex</i>	The instance of this subfield within the record. Use zero for the first instance.
<i>pnSuccess</i>	Pointer to an int which will be set to TRUE if the fetch succeeds, or FALSE if it fails. Use NULL if you don't want to check success.

Returns

The value of the subfield, or zero if it failed for some reason.

9.21.2.13 int DDFRecord::GetIntSubfield (const char * *pszField*, int *iFieldIndex*, const char * *pszSubfield*, int *iSubfieldIndex*, int * *pnSuccess* = NULL)

Fetch value of a subfield as an integer. This is a convenience function for fetching a subfield of a field within this record.

Parameters

<i>pszField</i>	The name of the field containing the subfield.
<i>iFieldIndex</i>	The instance of this field within the record. Use zero for the first instance of this field.
<i>pszSubfield</i>	The name of the subfield within the selected field.
<i>iSubfieldIndex</i>	The instance of this subfield within the record. Use zero for the first instance.
<i>pnSuccess</i>	Pointer to an int which will be set to TRUE if the fetch succeeds, or FALSE if it fails. Use NULL if you don't want to check success.

Returns

The value of the subfield, or zero if it failed for some reason.

9.21.2.14 DDFModule* DDFRecord::GetModule () [inline]

Fetch the [DDFModule](#) with which this record is associated.

9.21.2.15 const char * DDFRecord::GetStringSubfield (const char * *pszField*, int *iFieldIndex*, const char * *pszSubfield*, int *iSubfieldIndex*, int * *pnSuccess* = NULL)

Fetch value of a subfield as a string. This is a convenience function for fetching a subfield of a field within this record.

Parameters

<i>pszField</i>	The name of the field containing the subfield.
<i>iFieldIndex</i>	The instance of this field within the record. Use zero for the first instance of this field.
<i>pszSubfield</i>	The name of the subfield within the selected field.
<i>iSubfieldIndex</i>	The instance of this subfield within the record. Use zero for the first instance.
<i>pnSuccess</i>	Pointer to an int which will be set to TRUE if the fetch succeeds, or FALSE if it fails. Use NULL if you don't want to check success.

Returns

The value of the subfield, or NULL if it failed for some reason. The returned pointer is to internal data and should not be modified or freed by the application.

9.21.2.16 int DDFRecord::ResizeField (DDFField * poField, int nNewDataSize)

Alter field data size within record.

This method will rearrange a [DDFRecord](#) altering the amount of space reserved for one of the existing fields. All following fields will be shifted accordingly. This includes updating the [DDFField](#) infos, and actually moving stuff within the data array after reallocating to the desired size.

Parameters

<i>poField</i>	the field to alter.
<i>nNewDataSize</i>	the number of data bytes to be reserved for the field.

Returns

TRUE on success or FALSE on failure.

9.21.2.17 int DDFRecord::SetFieldRaw (DDFField * poField, int iIndexWithinField, const char * pachRawData, int nRawDataSize)

Set the raw contents of a field instance.

Parameters

<i>poField</i>	the field to set data within.
<i>iIndexWithinField</i>	The instance of this field to replace. Must be a value between 0 and GetRepeatCount(). If GetRepeatCount() is used, a new instance of the field is appended.
<i>pachRawData</i>	the raw data to replace this field instance with.
<i>nRawDataSize</i>	the number of bytes pointed to by pachRawData.

Returns

TRUE on success or FALSE on failure.

9.21.2.18 int DDFRecord::SetFloatSubfield (const char * pszField, int iFieldIndex, const char * pszSubfield, int iSubfieldIndex, double dfnewValue)

Set a float subfield in record.

The value of a given subfield is replaced with a new float value formatted appropriately.

Parameters

<i>pszField</i>	the field name to operate on.
<i>iFieldIndex</i>	the field index to operate on (zero based).
<i>pszSubfield</i>	the subfield name to operate on.
<i>iSubfieldIndex</i>	the subfield index to operate on (zero based).
<i>dfnewValue</i>	the new value to place in the subfield.

Returns

TRUE if successful, and FALSE if not.

9.21.2.19 `int DDFRecord::SetIntSubfield (const char * pszField, int iFieldIndex, const char * pszSubfield, int iSubfieldIndex, int nnewValue)`

Set an integer subfield in record.

The value of a given subfield is replaced with a new integer value formatted appropriately.

Parameters

<i>pszField</i>	the field name to operate on.
<i>iFieldIndex</i>	the field index to operate on (zero based).
<i>pszSubfield</i>	the subfield name to operate on.
<i>iSubfieldIndex</i>	the subfield index to operate on (zero based).
<i>nnewValue</i>	the new value to place in the subfield.

Returns

TRUE if successful, and FALSE if not.

9.21.2.20 `int DDFRecord::SetStringSubfield (const char * pszField, int iFieldIndex, const char * pszSubfield, int iSubfieldIndex, const char * pszValue, int nValueLength = -1)`

Set a string subfield in record.

The value of a given subfield is replaced with a new string value formatted appropriately.

Parameters

<i>pszField</i>	the field name to operate on.
<i>iFieldIndex</i>	the field index to operate on (zero based).
<i>pszSubfield</i>	the subfield name to operate on.
<i>iSubfieldIndex</i>	the subfield index to operate on (zero based).
<i>pszValue</i>	the new string to place in the subfield. This may be arbitrary binary bytes if nValueLength is specified.
<i>nValueLength</i>	the number of valid bytes in pszValue, may be -1 to internally fetch with strlen().

Returns

TRUE if successful, and FALSE if not.

9.21.2.21 `int DDFRecord::Write ()`

Write record out to module.

This method writes the current record to the module to which it is attached. Normally this would be at the end of the file, and only used for modules newly created with `DDFModule::Create()`. Rewriting existing records is not supported at this time. Calling `Write()` multiple times on a `DDFRecord` will result in multiple copies being written at the end of the module.

Returns

TRUE on success or FALSE on failure.

The documentation for this class was generated from the following files:

- iso8211.h
- ddfrecord.cpp

9.22 DDFSubfieldDefn Class Reference

```
#include <iso8211.h>
```

Public Types

- enum [DDFBinaryFormat](#)

Public Member Functions

- const char * [GetName](#) ()
- const char * [GetFormat](#) ()
- DDFDataType [GetType](#) ()
- double [ExtractFloatData](#) (const char *pachData, int nMaxBytes, int *pnConsumedBytes)
- int [ExtractIntData](#) (const char *pachData, int nMaxBytes, int *pnConsumedBytes)
- const char * [ExtractStringData](#) (const char *pachData, int nMaxBytes, int *pnConsumedBytes)
- int [GetDataLength](#) (const char *, int, int *)
- void [DumpData](#) (const char *pachData, int nMaxBytes, FILE *fp)
- int [FormatStringValue](#) (char *pachData, int nBytesAvailable, int *pnBytesUsed, const char *pszValue, int nValueLength=-1)
- int [FormatIntValue](#) (char *pachData, int nBytesAvailable, int *pnBytesUsed, int nNewValue)
- int [FormatFloatValue](#) (char *pachData, int nBytesAvailable, int *pnBytesUsed, double dfNewValue)
- int [GetWidth](#) ()
- int [GetDefaultValue](#) (char *pachData, int nBytesAvailable, int *pnBytesUsed)
- void [Dump](#) (FILE *fp)

9.22.1 Detailed Description

Information from the DDR record describing one subfield of a [DDFFieldDefn](#). All subfields of a field will occur in each occurrence of that field (as a [DDFField](#)) in a [DDFRecord](#). Subfield's actually contain formatted data (as instances within a record).

9.22.2 Member Enumeration Documentation

9.22.2.1 enum DDFSubfieldDefn::DDFBinaryFormat

Binary format: this is the digit immediately following the B or b for binary formats.

9.22.3 Member Function Documentation

9.22.3.1 void DDFSubfieldDefn::Dump (FILE * *fp*)

Write out subfield definition info to debugging file.

A variety of information about this field definition is written to the give debugging file handle.

Parameters

<i>fp</i>	The standard io file handle to write to. ie. stderr
-----------	---

9.22.3.2 void DDFSubfieldDefn::DumpData (const char * *pachData*, int *nMaxBytes*, FILE * *fp*)

Dump subfield value to debugging file.

Parameters

<i>pachData</i>	Pointer to data for this subfield.
<i>nMaxBytes</i>	Maximum number of bytes available in pachData.
<i>fp</i>	File to write report to.

9.22.3.3 double DDFSubfieldDefn::ExtractFloatData (const char * *pachSourceData*, int *nMaxBytes*, int * *pnConsumedBytes*)

Extract a subfield value as a float. Given a pointer to the data for this subfield (from within a [DDFRecord](#)) this method will return the floating point data for this subfield. The number of bytes consumed as part of this field can also be fetched. This method may be called for any type of subfield, and will return zero if the subfield is not numeric.

Parameters

<i>pachSourceData</i>	The pointer to the raw data for this field. This may have come from DDFRecord::GetData() , taking into account skip factors over previous subfields data.
<i>nMaxBytes</i>	The maximum number of bytes that are accessable after pachSourceData.
<i>pnConsumed-Bytes</i>	Pointer to an integer into which the number of bytes consumed by this field should be written. May be NULL to ignore. This is used as a skip factor to increment pachSourceData to point to the next subfields data.

Returns

The subfield's numeric value (or zero if it isn't numeric).

See Also

[ExtractIntData\(\)](#), [ExtractStringData\(\)](#)

9.22.3.4 int DDFSubfieldDefn::ExtractIntData (const char * *pachSourceData*, int *nMaxBytes*, int * *pnConsumedBytes*)

Extract a subfield value as an integer. Given a pointer to the data for this subfield (from within a [DDFRecord](#)) this method will return the int data for this subfield. The number of bytes consumed as part of this field can also be fetched. This method may be called for any type of subfield, and will return zero if the subfield is not numeric.

Parameters

<i>pachSourceData</i>	The pointer to the raw data for this field. This may have come from DDFRecord::GetData() , taking into account skip factors over previous subfields data.
<i>nMaxBytes</i>	The maximum number of bytes that are accessable after pachSourceData.
<i>pnConsumed-Bytes</i>	Pointer to an integer into which the number of bytes consumed by this field should be written. May be NULL to ignore. This is used as a skip factor to increment pachSourceData to point to the next subfields data.

Returns

The subfield's numeric value (or zero if it isn't numeric).

See Also

[ExtractFloatData\(\)](#), [ExtractStringData\(\)](#)

9.22.3.5 const char * DDFSubfieldDefn::ExtractStringData (const char * *pachSourceData*, int *nMaxBytes*, int * *pnConsumedBytes*)

Extract a zero terminated string containing the data for this subfield. Given a pointer to the data for this subfield (from within a [DDFRecord](#)) this method will return the data for this subfield. The number of bytes consumed as part of this field can also be fetched. This number may be one longer than the string length if there is a terminator character used.

This function will return the raw binary data of a subfield for types other than DDFString, including data past zero chars. This is the standard way of extracting DDFBinaryString subfields for instance.

Parameters

<i>pachSourceData</i>	The pointer to the raw data for this field. This may have come from DDFRecord::GetData() , taking into account skip factors over previous subfields data.
<i>nMaxBytes</i>	The maximum number of bytes that are accessable after pachSourceData.
<i>pnConsumed-Bytes</i>	Pointer to an integer into which the number of bytes consumed by this field should be written. May be NULL to ignore. This is used as a skip factor to increment pachSourceData to point to the next subfields data.

Returns

A pointer to a buffer containing the data for this field. The returned pointer is to an internal buffer which is invalidated on the next [ExtractStringData\(\)](#) call on this DDFSubfieldDefn(). It should not be freed by the application.

See Also

[ExtractIntData\(\)](#), [ExtractFloatData\(\)](#)

9.22.3.6 int DDFSubfieldDefn::FormatFloatValue (char * *pachData*, int *nBytesAvailable*, int * *pnBytesUsed*, double *dfnewValue*)

Format float subfield value.

Returns a buffer with the passed in float value reformatted in a way suitable for storage in a [DDFField](#) for this subfield.

9.22.3.7 int DDFSubfieldDefn::FormatIntValue (char * *pachData*, int *nBytesAvailable*, int * *pnBytesUsed*, int *nNewValue*)

Format int subfield value.

Returns a buffer with the passed in int value reformatted in a way suitable for storage in a [DDFField](#) for this subfield.

9.22.3.8 int DDFSubfieldDefn::FormatStringValue (char * *pachData*, int *nBytesAvailable*, int * *pnBytesUsed*, const char * *pszValue*, int *nValueLength* = -1)

Format string subfield value.

Returns a buffer with the passed in string value reformatted in a way suitable for storage in a [DDFField](#) for this subfield.

9.22.3.9 int DDFSubfieldDefn::GetDataLength (const char * *pachSourceData*, int *nMaxBytes*, int * *pnConsumedBytes*)

Scan for the end of variable length data. Given a pointer to the data for this subfield (from within a [DDFRecord](#)) this method will return the number of bytes which are data for this subfield. The number of bytes consumed as part of this field can also be fetched. This number may be one longer than the length if there is a terminator character used.

This method is mainly for internal use, or for applications which want the raw binary data to interpret themselves. Otherwise use one of [ExtractStringData\(\)](#), [ExtractIntData\(\)](#) or [ExtractFloatData\(\)](#).

Parameters

<i>pachSourceData</i>	The pointer to the raw data for this field. This may have come from DDFRecord::GetData() , taking into account skip factors over previous subfields data.
<i>nMaxBytes</i>	The maximum number of bytes that are accessable after <i>pachSourceData</i> .
<i>pnConsumed-Bytes</i>	Pointer to an integer into which the number of bytes consumed by this field should be written. May be NULL to ignore.

Returns

The number of bytes at *pachSourceData* which are actual data for this record (not including unit, or field terminator).

9.22.3.10 int DDFSubfieldDefn::GetDefaultValue (char * *pachData*, int *nBytesAvailable*, int * *pnBytesUsed*)

Get default data.

Returns the default subfield data contents for this subfield definition. For variable length numbers this will normally be "0<unit-terminator>". For variable length strings it will be "<unit-terminator>". For fixed length numbers it is zero filled. For fixed length strings it is space filled. For binary numbers it is binary zero filled.

Parameters

<i>pachData</i>	the buffer into which the returned default will be placed. May be NULL if just querying default size.
<i>nBytesAvailable</i>	the size of <i>pachData</i> in bytes.
<i>pnBytesUsed</i>	will receive the size of the subfield default data in bytes.

Returns

TRUE on success or FALSE on failure or if the passed buffer is too small to hold the default.

9.22.3.11 `const char* DDFSubfieldDefn::GetFormat() [inline]`

Get pointer to subfield format string

9.22.3.12 `const char* DDFSubfieldDefn::GetName() [inline]`

Get pointer to subfield name.

9.22.3.13 `DDFDataType DDFSubfieldDefn::GetType() [inline]`

Get the general type of the subfield. This can be used to determine which of [ExtractFloatData\(\)](#), [ExtractIntData\(\)](#) or [ExtractStringData\(\)](#) should be used.

Returns

The subfield type. One of DDFInt, DDFFloat, DDFString or DDFBinaryString.

9.22.3.14 `int DDFSubfieldDefn::GetWidth() [inline]`

Get the subfield width (zero for variable).

The documentation for this class was generated from the following files:

- iso8211.h
- ddfsubfielddefn.cpp

9.23 DefaultCSVFileNameTLS Struct Reference

The documentation for this struct was generated from the following file:

- cpl_csv.cpp

9.24 errHandler Struct Reference

The documentation for this struct was generated from the following file:

- cpl_error.cpp

9.25 file_in_zip_read_info_s Struct Reference

The documentation for this struct was generated from the following file:

- cpl_minizip_unzip.cpp

9.26 FindFileTLS Struct Reference

The documentation for this struct was generated from the following file:

- cpl_findfile.cpp

9.27 GZipSnapshot Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_vsil_gzip.cpp`

9.28 linkedlist_data_s Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minizip_zip.cpp`

9.29 linkedlist_datablock_internal_s Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minizip_zip.cpp`

9.30 ParseContext Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minixml.cpp`

9.31 SDTS_CATD Class Reference

```
#include <sdts_al.h>
```

Public Member Functions

- `const char * GetEntryTypeDesc (int)`
- `const char * GetEntryFilePath (int)`
- `SDTSLayerType GetEntryType (int)`

9.31.1 Detailed Description

Class for accessing the CATD (Catalog Directory) file containing a list of all other files (modules) in the transfer.

9.31.2 Member Function Documentation

9.31.2.1 `const char * SDTS_CATD::GetEntryFilePath (int iEntry)`

Fetch the full filename of the requested module.

Parameters

<code>iEntry</code>	The module index within the CATD catalog. A number from zero to <code>GetEntryCount()</code> -1.
---------------------	--

Returns

A pointer to an internal string containing the filename. This string should not be altered, or freed by the application.

9.31.2.2 SDTSLayerType SDTS_CATD::GetEntryType (int *iEntry*)

Fetch the enumerated type of a module in the catalog.

Parameters

<i>iEntry</i>	The module index within the CATD catalog. A number from zero to GetEntryCount()-1.
---------------	--

Returns

A value from the SDTSLayerType enumeration indicating the type of the module, and indicating the corresponding type of reader.

- SLTPoint: Read with [SDTSPointReader](#), underlying type of Point–Node.
- SLTLine: Read with [SDTSLineReader](#), underlying type of Line.
- SLAttr: Read with [SDTSAttrReader](#), underlying type of Attribute Primary or Attribute Secondary.
- SLTPolygon: Read with [SDTSPolygonReader](#), underlying type of Polygon.

9.31.2.3 const char * SDTS_CATD::GetEntryTypeDesc (int *iEntry*)

Fetch the type description of a module in the catalog.

Parameters

<i>iEntry</i>	The module index within the CATD catalog. A number from zero to GetEntryCount()-1.
---------------	--

Returns

A pointer to an internal string with the type description for this module. This is from the CATD file (subfield TYPE of field CATD), and will be something like "Attribute Primary".

The documentation for this class was generated from the following files:

- sdtscatd.h
- sdtscatd.cpp

9.32 SDTS_CATDEntry Class Reference

The documentation for this class was generated from the following file:

- sdtscatd.cpp

9.33 SDTS_IREF Class Reference

```
#include <sdtscatd.h>
```

9.33.1 Detailed Description

Class holding SDTS IREF (internal reference) information, internal coordinate system format, scaling and resolution. This object isn't normally needed by applications.

The documentation for this class was generated from the following files:

- `sdts_al.h`
- `sdtsiref.cpp`

9.34 SDTS_XREF Class Reference

```
#include <sdts_al.h>
```

Public Attributes

- `char * pszSystemName`
- `char * pszDatum`
- `int nZone`

9.34.1 Detailed Description

Class for reading the XREF (external reference) module containing the data projection definition.

9.34.2 Member Data Documentation

9.34.2.1 int SDTS_XREF::nZone

Zone number for UTM and SPCS projections, from the ZONE field.

9.34.2.2 char* SDTS_XREF::pszDatum

Horizontal datum name, from the HDAT field. One of NAS, NAX, WGA, WGB, WGC, WGE.

9.34.2.3 char* SDTS_XREF::pszSystemName

Projection system name, from the RSNM field. One of GEO, SPCS, UTM, UPS, OTHR, UNSP.


The documentation for this class was generated from the following files:

- `sdts_al.h`
- `sdtsxref.cpp`

9.35 SDTSAtrReader Class Reference

```
#include <sdts_al.h>
```

Inheritance diagram for SDTSAtrReader:



Public Member Functions

- int [IsSecondary \(\)](#)

9.35.1 Detailed Description

Class for reading [SDTSAAttrRecord](#) features from a primary or secondary attribute module.

9.35.2 Member Function Documentation

9.35.2.1 int SDTSAAttrReader::IsSecondary () [inline]

Returns TRUE if this is a Attribute Secondary layer rather than an Attribute Primary layer.


The documentation for this class was generated from the following files:

- [sdts_al.h](#)
- [sdtsattrreader.cpp](#)

9.36 SDTSAAttrRecord Class Reference

```
#include <sdts_al.h>
```

Inheritance diagram for SDTSAAttrRecord:



Public Member Functions

- virtual void [Dump \(FILE *\)](#)

Public Attributes

- [DDFRecord * poWholeRecord](#)
- [DDFField * poATTR](#)

9.36.1 Detailed Description

SDTS attribute record feature, as read from A* modules by [SDTSAAttrReader](#).

Note that even though [SDTSAAttrRecord](#) is derived from [SDTSFeature](#), there are never any attribute records associated with attribute records using the aoATID[] mechanism. [SDTSFeature::nAttributes](#) will always be zero.

9.36.2 Member Function Documentation

9.36.2.1 void SDTSAtrRecord::Dump (FILE *) [virtual]

Dump readable description of feature to indicated stream.

Implements [SDTSFeature](#).

9.36.3 Member Data Documentation

9.36.3.1 DDFField* SDTSAtrRecord::poATTR

The ATTR [DDFRecord](#) with the user attribute. Each subfield is a attribute value.

9.36.3.2 DDFRecord* SDTSAtrRecord::poWholeRecord

The entire [DDFRecord](#) read from the file.

The documentation for this class was generated from the following files:

- [sdts_al.h](#)
- [sdtsattrreader.cpp](#)

9.37 SDTSdataset Class Reference

Friends

- class [SDTSRasterBand](#)


The documentation for this class was generated from the following file:

- [sdtsdataset.cpp](#)

9.38 SDTSFeature Class Reference

```
#include <sdts_al.h>
```

Inheritance diagram for SDTSFeature:



Public Member Functions

- virtual void [Dump](#) (FILE *)=0

Public Attributes

- `SDTSModId oModId`
- `int nAttributes`
- `SDTSModId * paoATID`

9.38.1 Detailed Description

Base class for various SDTS features classes, providing a generic module identifier, and list of attribute references.

9.38.2 Member Function Documentation

9.38.2.1 `virtual void SDTSFeature::Dump (FILE *) [pure virtual]`

Dump readable description of feature to indicated stream.

Implemented in `SDTSSRawPolygon`, `SDTSSRawPoint`, `SDTSArrRecord`, and `SDTSSRawLine`.

9.38.3 Member Data Documentation

9.38.3.1 `int SDTSFeature::nAttributes`

Number of attribute links (`aoATID[]`) on this feature.

9.38.3.2 `SDTSModId SDTSFeature::oModId`

Unique identifier for this record/feature within transfer.

9.38.3.3 `SDTSModId* SDTSFeature::paoATID`

List of `nAttributes` attribute record identifiers related to this feature.


The documentation for this class was generated from the following files:

- `sdts_al.h`
- `sdtslib.cpp`

9.39 SDTSIndexedReader Class Reference

```
#include <sdts_al.h>
```

Inheritance diagram for SDTSIndexedReader:



Public Member Functions

- `SDTSFeature * GetNextFeature ()`
- `virtual void Rewind ()`
- `void FillIndex ()`
- `void ClearIndex ()`
- `int IsIndexed ()`
- `SDTSFeature * GetIndexedFeatureRef (int)`
- `char ** ScanModuleReferences (const char *="ATID")`

9.39.1 Detailed Description

Base class for all the `SDTSFeature` type readers. Provides feature caching semantics and fetching based on a record number.

9.39.2 Member Function Documentation

9.39.2.1 void SDTSIndexedReader::ClearIndex ()

Free all features in the index (if filled).

After this the reader is considered to not be indexed, and `IsIndexed()` will return FALSE until the index is forcibly filled again.

9.39.2.2 void SDTSIndexedReader::FillIndex ()

Read all features into a memory indexed cached.

The `ClearIndex()` method can be used to free all indexed features. `FillIndex()` does nothing, if an index has already been built.

9.39.2.3 SDTSFeature * SDTSIndexedReader::GetIndexedFeatureRef (int iRecordId)

Fetch a feature based on its record number.

This method will forceably fill the feature cache, reading all the features in the file into memory, if they haven't already been loaded. The `ClearIndex()` method can be used to flush this cache when no longer needed.

Parameters

<code>iRecordId</code>	the record to fetch, normally based on the nRecord field of an <code>SDTSMoidl</code> .
------------------------	---

Returns

a pointer to an internal feature (not to be deleted) or NULL if there is no matching feature.

9.39.2.4 SDTSFeature * SDTSIndexedReader::GetNextFeature ()

Fetch the next available feature from this reader.

The returned `SDTSFeature *` is to an internal indexed object if the `IsIndexed()` method returns TRUE, otherwise the returned feature becomes the responsibility of the caller to destroy with `delete`.

Note that the `Rewind()` method can be used to start over at the beginning of the modules feature list.

Returns

next feature, or NULL if no more are left. Please review above ownership/delete semantics.

9.39.2.5 int SDTSIndexedReader::IsIndexed()

Returns TRUE if the module is indexed, otherwise it returns FALSE.

If the module is indexed all the feature have already been read into memory, and searches based on the record number can be performed efficiently.

9.39.2.6 void SDTSIndexedReader::Rewind() [virtual]

Rewind so that the next feature returned by [GetNextFeature\(\)](#) will be the first in the module.

9.39.2.7 char ** SDTSIndexedReader::ScanModuleReferences(const char * pszFName = "ATID")

Scan an entire SDTS module for record references with the given field name.

The fields are required to have a MODN subfield from which the module is extracted.

This method is normally used to find all the attribute modules referred to by a point, line or polygon module to build a unified schema.

This method will have the side effect of rewinding unindexed readers because the scanning operation requires reading all records in the module from disk.

Parameters

<code>pszFName</code>	the field name to search for. By default "ATID" is used.
-----------------------	--

Returns

a NULL terminated list of module names. Free with [CSLDestroy\(\)](#).


The documentation for this class was generated from the following files:

- `sdts_al.h`
- `sdtsindexedreader.cpp`

9.40 SDTSLineReader Class Reference

```
#include <sdts_al.h>
```

Inheritance diagram for SDTSLineReader:

**Public Member Functions**

- void [AttachToPolygons \(SDTSTransfer *, int iPolyLayer\)](#)

9.40.1 Detailed Description

Reader for SDTS line modules.

Returns [SDTSSRawLine](#) features. Normally readers are instantiated with the `SDTSTransfer::GetIndexedReader()` method.

9.40.2 Member Function Documentation

9.40.2.1 void SDTSLinereader::AttachToPolygons (`SDTSTransfer * poTransfer, int iTar`getPolyLayer)

Attach lines in this module to their polygons as the first step in polygon formation.

See also the [SDTSSRawPolygon::AssembleRings\(\)](#) method.

Parameters

<code>poTransfer</code>	the SDTSTransfer of this SDTSLinereader , and from which the related SDTSPolygonReader will be instantiated.
<code>iTargetPolyLayer</code>	the polygon reader instance number, used to avoid processing lines for other layers.

The documentation for this class was generated from the following files:

- `sdts_al.h`
- `sdtslinereader.cpp`

9.41 SDTSModId Class Reference

```
#include <sdts_al.h>
```

Public Attributes

- char `szModule` [8]
- long `nRecord`
- char `szOBRP` [8]

9.41.1 Detailed Description

Object representing a unique module/record identifier within an SDTS transfer.

9.41.2 Member Data Documentation

9.41.2.1 long SDTSModId::nRecord

The record within the module referred to. This is -1 for unused SDTSModIds.

9.41.2.2 char SDTSModId::szModule[8]

The module name, such as PC01, containing the indicated record.

9.41.2.3 char SDTSModId::szOBRP[8]

The "role" of this record within the module. This is normally empty for references, but set in the oModId member of a feature.


The documentation for this class was generated from the following files:

- `sdts_al.h`
- `sdtslib.cpp`

9.42 SDTSPointReader Class Reference

```
#include <sdts_al.h>
```

Inheritance diagram for SDTSPointReader:



Additional Inherited Members

9.42.1 Detailed Description

Class for reading [SDTSPRawPoint](#) features from a point module (type NA, NO or NP).


The documentation for this class was generated from the following files:

- `sdts_al.h`
- `sdtspointreader.cpp`

9.43 SDTSPolygonReader Class Reference

```
#include <sdts_al.h>
```

Inheritance diagram for SDTSPolygonReader:



Public Member Functions

- void [AssembleRings](#) (`SDTSTransfer` *, int iPolyLayer)

9.43.1 Detailed Description

Class for reading [SDTSPRawPolygon](#) features from a polygon (PC*) module.

9.43.2 Member Function Documentation

9.43.2.1 void SDTSPolygonReader::AssembleRings (*SDTSTransfer* * *poTransfer*, int *iPolyLayer*)

Assemble geometry for a polygon transfer.

This method takes care of attaching lines from all the line layers in this transfer to this polygon layer, assembling the lines into rings on the polygons, and then cleaning up unnecessary intermediate results.

Currently this method will leave the line layers rewound to the beginning but indexed, and the polygon layer rewound but indexed. In the future it may restore reading positions, and possibly flush line indexes if they were not previously indexed.

This method does nothing if the rings have already been assembled on this layer using this method.

See [SDTSRawPolygon::AssembleRings\(\)](#) for more information on how the lines are assembled into rings.

Parameters

<i>poTransfer</i>	the SDTSTransfer that this reader is a part of. Used to get a list of line layers that might be needed.
<i>iPolyLayer</i>	the polygon reader instance number, used to avoid processing lines for other layers.

The documentation for this class was generated from the following files:

- [sdts_al.h](#)
- [sdtpolygonreader.cpp](#)

9.44 SDTSRasterBand Class Reference

Friends

- class [SDTSDataset](#)

The documentation for this class was generated from the following file:

- [sdtsdataset.cpp](#)

9.45 SDTSRasterReader Class Reference

```
#include <sdts_al.h>
```

Public Member Functions

- int [GetRasterType](#) ()
- int [GetTransform](#) (double *)
- int [GetMinMax](#) (double *pdfMin, double *pdfMax, double dfNoData)
- int [GetXSize](#) ()
- int [GetYSize](#) ()
- int [GetBlockXSize](#) ()
- int [GetBlockYSize](#) ()
- int [GetBlock](#) (int nXOffset, int nYOffset, void *pData)

9.45.1 Detailed Description

Class for reading raster data from a raster layer.

This class is somewhat unique among the reader classes in that it isn't derived from SDTSIndexedFeature, and it doesn't return "features". Instead it is used to read raster blocks, in the natural block size of the dataset.

9.45.2 Member Function Documentation

9.45.2.1 int SDTSRasterReader::GetBlock (int *nXOffset*, int *nYOffset*, void * *pData*)

Read a block of raster data from the file.

Parameters

<i>nXOffset</i>	X block offset into the file. Normally zero for scanline organized raster files.
<i>nYOffset</i>	Y block offset into the file. Normally the scanline offset from top of raster for scanline organized raster files.
<i>pData</i>	pointer to GInt16 (signed short) buffer of data into which to read the raster.

Returns

TRUE on success and FALSE on error.

9.45.2.2 int SDTSRasterReader::GetBlockXSize () [inline]

Fetch the width of a source block (usually same as raster width).

9.45.2.3 int SDTSRasterReader::GetBlockYSize () [inline]

Fetch the height of a source block (usually one).

9.45.2.4 int SDTSRasterReader::GetMinMax (double * *pdfMin*, double * *pdfMax*, double *dfNoData*)

Fetch the minimum and maximum raster values that occur in the file.

Note this operation current results in a scan of the entire file.

Parameters

<i>pdfMin</i>	variable in which the minimum value encountered is returned.
<i>pdfMax</i>	variable in which the maximum value encountered is returned.
<i>dfNoData</i>	a value to ignore when computing min/max, defaults to -32766.

Returns

TRUE on success, or FALSE if an error occurs.

9.45.2.5 int SDTSRasterReader::GetRasterType ()

Fetch the pixel data type.

Returns one of SDTS_RT_INT16 (1) or SDTS_RT_FLOAT32 (6) indicating the type of buffer that should be passed to [GetBlock\(\)](#).

9.45.2.6 int SDTSRasterReader::GetTransform (double * *padfTransformOut*)

Fetch the transformation between pixel/line coordinates and georeferenced coordinates.

Returns

TRUE is returned, indicating success.

The padfTransformOut array consists of six values. The pixel/line coordinate (Xp,Yp) can be related to a georeferenced coordinate (Xg,Yg) or (Easting, Northing).

$$\begin{aligned} Xg &= \text{padfTransformOut}[0] + Xp * \text{padfTransform}[1] + Yp * \text{padfTransform}[2] \\ Yg &= \text{padfTransformOut}[3] + Xp * \text{padfTransform}[4] + Yp * \text{padfTransform}[5] \end{aligned}$$

In other words, for a north up image the top left corner of the top left pixel is at georeferenced coordinate (padfTransform[0],padfTransform[3]) the pixel width is padfTransform[1], the pixel height is padfTransform[5] and padfTransform[2] and padfTransform[4] will be zero.

9.45.2.7 int SDTSRasterReader::GetXSize () [inline]

Fetch the raster width.

Returns

the width in pixels.

9.45.2.8 int SDTSRasterReader::GetYSize () [inline]

Fetch the raster height.

Returns

the height in pixels.


The documentation for this class was generated from the following files:

- sdtc_al.h
- sdtcrasterreader.cpp

9.46 SDTSRawLine Class Reference

```
#include <sdtc_al.h>
```

Inheritance diagram for SDTSRawLine:



Public Member Functions

- void [Dump](#) (FILE *)

Public Attributes

- int [nVertices](#)
- double * [padfX](#)
- double * [padfY](#)
- double * [padfZ](#)
- SDTSModId [oLeftPoly](#)
- SDTSModId [oRightPoly](#)
- SDTSModId [oStartNode](#)
- SDTSModId [oEndNode](#)

9.46.1 Detailed Description

SDTS line feature, as read from LE* modules by [SDTSLineReader](#).

9.46.2 Member Function Documentation

9.46.2.1 void SDTSRawLine::Dump (FILE *) [virtual]

Dump readable description of feature to indicated stream.

Implements [SDTSFeature](#).

9.46.3 Member Data Documentation

9.46.3.1 int SDTSRawLine::nVertices

Number of vertices in the padfX, padfY and padfZ arrays.

9.46.3.2 SDTSModId SDTSRawLine::oEndNode

Identifier for the end node of this line. This is the SDTS ENID subfield.

9.46.3.3 SDTSModId SDTSRawLine::oLeftPoly

Identifier of polygon to left of this line. This is the SDTS PIDL subfield.

9.46.3.4 SDTSModId SDTSRawLine::oRightPoly

Identifier of polygon to right of this line. This is the SDTS PIDR subfield.

9.46.3.5 SDTSModId SDTSRawLine::oStartNode

Identifier for the start node of this line. This is the SDTS SNID subfield.

9.46.3.6 double* SDTSRawLine::padfX

List of nVertices X coordinates.

9.46.3.7 double* SDTSRawLine::padfY

List of nVertices Y coordinates.

9.46.3.8 double* SDTSRawLine::padfZ

List of nVertices Z coordinates - currently always zero.


The documentation for this class was generated from the following files:

- [sdts_al.h](#)
- [sdtslinereader.cpp](#)

9.47 SDTSRawPoint Class Reference

```
#include <sdts_al.h>
```

Inheritance diagram for SDTSRawPoint:



Public Member Functions

- [virtual void Dump \(FILE *\)](#)

Public Attributes

- [double dfX](#)
- [double dfY](#)
- [double dfZ](#)
- [SDTSMoId oAreald](#)

9.47.1 Detailed Description

Object containing a point feature (type NA, NO or NP).

9.47.2 Member Function Documentation

9.47.2.1 void SDTSRawPoint::Dump (FILE *) [virtual]

Dump readable description of feature to indicated stream.

Implements [SDTSFeature](#).

9.47.3 Member Data Documentation

9.47.3.1 double SDTSRawPoint::dfX

X coordinate of point.

9.47.3.2 double SDTSRawPoint::dfY

Y coordinate of point.

9.47.3.3 double SDTSRawPoint::dfZ

Z coordinate of point.

9.47.3.4 SDTSMoid SDTSRawPoint::oAreaId

Optional identifier of area marked by this point (ie. PC01:27).


The documentation for this class was generated from the following files:

- `sdts_al.h`
- `sdtspointreader.cpp`

9.48 SDTSRawPolygon Class Reference

```
#include <sdts_al.h>
```

Inheritance diagram for SDTSRawPolygon:



Public Member Functions

- int [AssembleRings \(\)](#)
- virtual void [Dump \(FILE *\)](#)

Public Attributes

- int [nRings](#)
- int [nVertices](#)
- int * [panRingStart](#)
- double * [padfX](#)
- double * [padfY](#)
- double * [padfZ](#)

9.48.1 Detailed Description

Class for holding information about a polygon feature.

When directly read from a polygon module, the polygon has no concept of its geometry. Just its ID, and references to attribute records. However, if the [SDTSLineReader::AttachToPolygons\(\)](#) method is called on the module containing the lines forming the polygon boundaries, then the nEdges/papoEdges information on the [SDTSRawPolygon](#) will be filled in.

Once this is complete the [AssembleRings\(\)](#) method can be used to fill in the nRings/nVertices/panRingStart/padfx/X/padfy/Y/padfZ information defining the ring geometry.

Note that the rings may not appear in any particular order, nor with any meaningful direction (clockwise or counter-clockwise).

9.48.2 Member Function Documentation

9.48.2.1 int SDTSRawPolygon::AssembleRings()

This method will assemble the edges associated with a polygon into rings, returning FALSE if problems are encountered during assembly.

Form border lines (arcs) into outer and inner rings.

See [SDTSPolygonReader::AssemblePolygons\(\)](#) for a simple one step process to assembling geometry for all polygons in a transfer.

This method will assemble the lines attached to a polygon into an outer ring, and zero or more inner rings. Before calling it is necessary that all the lines associated with this polygon have already been attached. Normally this is accomplished by calling [SDTSLineReader::AttachToPolygons\(\)](#) on all line layers that might contain edges related to this layer.

This method then forms the lines into rings. Rings are formed by:

1. Take a previously unconsumed line, and start a ring with it. Mark it as consumed, and keep track of its start and end node ids as being the start and end node ids of the ring.
2. If the rings start id is the same as the end node id then this ring is completely formed, return to step 1.
3. Search all unconsumed lines for a line with the same start or end node id as the rings current node id. If none are found then the assembly has failed. Return to step 1 but report failure on completion.
4. Once found, add the line to the current ring, dropping the duplicated vertex and reverse order if necessary. Mark the line as consumed, and update the rings end node id accordingly.
5. go to step 2.

Once ring assembly from lines is complete, another pass is made to order the rings such that the exterior ring is first, the first ring has counter-clockwise vertex ordering and the inner rings have clockwise vertex ordering. This is accomplished based on the assumption that the outer ring has the largest area, and using the +/- sign of area to establish direction of rings.

Returns

TRUE if all rings assembled without problems or FALSE if a problem occurred. If a problem occurs rings are still formed from all lines, but some of the rings will not be closed, and rings will have no particular order or direction.

9.48.2.2 void SDTSRawPolygon::Dump(FILE *) [virtual]

Dump readable description of feature to indicated stream.

Implements [SDTSFeature](#).

9.48.3 Member Data Documentation

9.48.3.1 int SDTSRawPolygon::nRings

Number of rings in assembled polygon.

9.48.3.2 int SDTSRawPolygon::nVertices

Total number of vertices in all rings of assembled polygon.

9.48.3.3 double* SDTSRawPolygon::padfX

List of nVertices X coordinates for the polygon (split over multiple rings via panRingStart).

9.48.3.4 double* SDTSRawPolygon::padfY

List of nVertices Y coordinates for the polygon (split over multiple rings via panRingStart).

9.48.3.5 double* SDTSRawPolygon::padfZ

List of nVertices Z coordinates for the polygon (split over multiple rings via panRingStart. The values are almost always zero).

9.48.3.6 int* SDTSRawPolygon::panRingStart

Offsets into padfX/padfY/padfZ for the beginning of each ring in the polygon. This array is nRings long.

The documentation for this class was generated from the following files:

- `sdts_al.h`
- `sdtspolygonreader.cpp`

9.49 SDTSTransfer Class Reference

```
#include <sdts_al.h>
```

Public Member Functions

- `int Open (const char *)`
- `int FindLayer (const char *)`
- `SDTSLayerType GetLayerType (int)`
- `int GetLayerCATDEntry (int)`
- `SDTSRasterReader * GetLayerRasterReader (int)`
- `SDTSIndexedReader * GetLayerIndexedReader (int)`
- `SDTS_CATD * GetCATD ()`
- `SDTS_XREF * GetXREF ()`
- `DDFField * GetAttr (SDTSModId *)`
- `int GetBounds (double *pdfMinX, double *pdfMinY, double *pdfMaxX, double *pdfMaxY)`

9.49.1 Detailed Description

Master class representing an entire SDTS transfer.

This class is used to open the transfer, to get a list of available feature layers, and to instantiate readers for those layers.

9.49.2 Member Function Documentation

9.49.2.1 int SDTSTransfer::FindLayer (const char * *pszModule*)

Fetch the [SDTSTransfer](#) layer number corresponding to a module name.

Parameters

<i>pszModule</i>	the name of the module to search for, such as "PC01".
------------------	---

Returns

the layer number (between 0 and GetLayerCount()-1 corresponding to the module, or -1 if it doesn't correspond to a layer.

9.49.2.2 DDFField * SDTSTransfer::GetAttr (SDTSModId * *poModId*)

Fetch the attribute fields given a particular module/record id.

Parameters

<i>poModId</i>	an attribute record identifier, normally taken from the aoATID[] array of an SDTSIndexed-Feature.
----------------	---

Returns

a pointer to the [DDFField](#) containing the user attribute values as subfields.

9.49.2.3 int SDTSTransfer::GetBounds (double * *pdfMinX*, double * *pdfMinY*, double * *pdfMaxX*, double * *pdfMaxY*)

Fetch approximate bounds for a transfer by scanning all point layers and raster layers.

For TVP datasets (where point layers are scanned) the results can, in theory miss some lines that go outside the bounds of the point layers. However, this isn't common since most TVP sets contain a bounding rectangle whose corners will define the most extreme extents.

Parameters

<i>pdfMinX</i>	western edge of dataset
<i>pdfMinY</i>	southern edge of dataset
<i>pdfMaxX</i>	eastern edge of dataset
<i>pdfMaxY</i>	northern edge of dataset

Returns

TRUE if success, or FALSE on a failure.

9.49.2.4 `SDTS_CATD* SDTSTransfer::GetCATD() [inline]`

Fetch the catalog object for this transfer.

Returns

pointer to the internally managed `SDTS_CATD` for the transfer.

9.49.2.5 `int SDTSTransfer::GetLayerCATDEntry(int iEntry)`

Fetch the CATD module index for a layer. This can be used to fetch details about the layer/module from the `SDTS_CATD` object, such as it's filename, and description.

Parameters

<code>iEntry</code>	the layer index from 0 to GetLayerCount()-1.
---------------------	--

Returns

the module index suitable for use with the various `SDTS_CATD` methods.

9.49.2.6 `SDTSIndexedReader * SDTSTransfer::GetLayerIndexedReader(int iEntry)`

Returns a pointer to a reader of the appropriate type to the requested layer.

Notes:

- The returned reader remains owned by the `SDTSTransfer`, and will be destroyed when the `SDTSTransfer` is destroyed. It should not be destroyed by the application.
- If an indexed reader was already created for this layer using `GetLayerIndexedReader()`, it will be returned instead of creating a new reader. Among other things this means that the returned reader may not be positioned to read from the beginning of the module, and may already have its index filled.
- The returned reader will be of a type appropriate to the layer. See `SDTSTransfer::GetLayerType()` to see what reader classes correspond to what layer types, so it can be cast accordingly (if necessary).

Parameters

<code>iEntry</code>	the index of the layer to instantiate a reader for. A value between 0 and GetLayerCount()-1.
---------------------	--

Returns

a pointer to an appropriate reader or NULL if the method fails.

9.49.2.7 `SDTSRasterReader * SDTSTransfer::GetLayerRasterReader(int iEntry)`

Instantiate an `SDTSRasterReader` for the indicated layer.

Parameters

<code>iEntry</code>	the index of the layer to instantiate a reader for. A value between 0 and GetLayerCount()-1.
---------------------	--

Returns

a pointer to a new [SDTSRasterReader](#) object, or NULL if the method fails.

NOTE: The reader returned from [GetLayerRasterReader\(\)](#) becomes the responsibility of the caller to delete, and isn't automatically deleted when the [SDTSTransfer](#) is destroyed. This method is different from the [GetLayerIndexedReader\(\)](#) method in this regard.

9.49.2.8 SDTSLayerType SDTSTransfer::GetLayerType (int *iEntry*)

Fetch type of requested feature layer.

Parameters

<i>iEntry</i>	the index of the layer to fetch information on. A value from zero to GetLayerCount()-1.
---------------	---

Returns

the layer type.

- SLTPoint: A point layer. An [SDTSPointReader](#) is returned by [SDTSTransfer::GetLayerIndexedReader\(\)](#).
- SLTLine: A line layer. An [SDTSLineReader](#) is returned by [SDTSTransfer::GetLayerIndexedReader\(\)](#).
- SLTAttr: An attribute primary or secondary layer. An [SDTSArrReader](#) is returned by [SDTSTransfer::GetLayerIndexedReader\(\)](#).
- SLTPoly: A polygon layer. An [SDTSPolygonReader](#) is returned by [SDTSTransfer::GetLayerIndexedReader\(\)](#).
- SLTRaster: A raster layer. [SDTSTransfer::GetLayerIndexedReader\(\)](#) is not implemented. Use [SDTSTransfer::GetLayerRasterReader\(\)](#) instead.

9.49.2.9 SDTS_XREF* SDTSTransfer::GetXREF() [inline]

Fetch the external reference object for this transfer.

Returns

pointer to the internally managed [SDTS_XREF](#) for the transfer.

9.49.2.10 int SDTSTransfer::Open (const char * *pszFilename*)

Open an SDTS transfer, and establish a list of data layers in the transfer.

Parameters

<i>pszFilename</i>	The name of the CATD file within the transfer.
--------------------	--

Returns

TRUE if the open success, or FALSE if it fails.

The documentation for this class was generated from the following files:

- [sdts_al.h](#)
- [sdtstransfer.cpp](#)

9.50 SFRegion Class Reference

The documentation for this class was generated from the following file:

- `cpl_vsil_sparsetfile.cpp`

9.51 StackContext Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minixml.cpp`

9.52 tm_unz_s Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minizip_unzip.h`

9.53 tm_zip_s Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minizip_zip.h`

9.54 unz_file_info_internal_s Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minizip_unzip.cpp`

9.55 unz_file_info_s Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minizip_unzip.h`

9.56 unz_file_pos_s Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minizip_unzip.h`

9.57 unz_global_info_s Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minizip_unzip.h`

9.58 unz_s Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minizip_unzip.cpp`

9.59 VSIArchiveContent Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_vsi_virtual.h`


9.60 VSIArchiveEntry Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_vsi_virtual.h`

9.61 VSIArchiveEntryFileOffset Class Reference

Inheritance diagram for VSIArchiveEntryFileOffset:




The documentation for this class was generated from the following files:

- `cpl_vsi_virtual.h`
- `cpl_vsil_abstract_archive.cpp`

9.62 VSIArchiveFilesystemHandler Class Reference

Inheritance diagram for VSIArchiveFilesystemHandler:




The documentation for this class was generated from the following files:

- `cpl_vsi_virtual.h`
- `cpl_vsil_abstract_archive.cpp`

9.63 VSIArchiveReader Class Reference

Inheritance diagram for VSIArchiveReader:




The documentation for this class was generated from the following files:

- `cpl_vsi_virtual.h`
- `cpl_vsil_abstract_archive.cpp`

9.64 VSIBufferedReaderHandle Class Reference

Inheritance diagram for VSIBufferedReaderHandle:



The documentation for this class was generated from the following file:

- `cpl_vsil_buffered_reader.cpp`


9.65 VSICacheChunk Class Reference

The documentation for this class was generated from the following file:

- `cpl_vsil_cache.cpp`

9.66 VSICachedFile Class Reference

Inheritance diagram for VSICachedFile:



The documentation for this class was generated from the following file:

- `cpl_vsil_cache.cpp`


9.67 VSIFileManager Class Reference

The documentation for this class was generated from the following files:

- `cpl_vsi_virtual.h`
- `cpl_vsil.cpp`

9.68 VSIFilesystemHandler Class Reference

Inheritance diagram for VSIFilesystemHandler:




The documentation for this class was generated from the following file:

- `cpl_vsi_virtual.h`

9.69 VSIGZipFilesystemHandler Class Reference

Inheritance diagram for VSIGZipFilesystemHandler:




The documentation for this class was generated from the following file:

- `cpl_vsil_gzip.cpp`

9.70 VSIGZipHandle Class Reference

Inheritance diagram for VSIGZipHandle:




The documentation for this class was generated from the following file:

- `cpl_vsil_gzip.cpp`

9.71 VSIGZipWriteHandle Class Reference

Inheritance diagram for VSIGZipWriteHandle:



The documentation for this class was generated from the following file:

- `cpl_vsil_gzip.cpp`


9.72 VSIMemFile Class Reference

The documentation for this class was generated from the following file:

- `cpl_vsi_mem.cpp`

9.73 VSIMemFilesystemHandler Class Reference

Inheritance diagram for VSIMemFilesystemHandler:




The documentation for this class was generated from the following file:

- `cpl_vsi_mem.cpp`

9.74 VSIMemHandle Class Reference

Inheritance diagram for VSIMemHandle:




The documentation for this class was generated from the following file:

- `cpl_vsi_mem.cpp`

9.75 VSISparseFileFilesystemHandler Class Reference

Inheritance diagram for VSISparseFileFilesystemHandler:




The documentation for this class was generated from the following file:

- `cpl_vsil_sparsefile.cpp`

9.76 VSISparseFileHandle Class Reference

Inheritance diagram for VSISparseFileHandle:




The documentation for this class was generated from the following file:

- `cpl_vsil_sparsefile.cpp`

9.77 VSIStdinFilesystemHandler Class Reference

Inheritance diagram for VSIStdinFilesystemHandler:




The documentation for this class was generated from the following file:

- `cpl_vsil_stdin.cpp`

9.78 VSIStdinHandle Class Reference

Inheritance diagram for VSIStdinHandle:




The documentation for this class was generated from the following file:

- `cpl_vsil_stdin.cpp`

9.79 VSIStdoutFilesystemHandler Class Reference

Inheritance diagram for VSIStdoutFilesystemHandler:




The documentation for this class was generated from the following file:

- `cpl_vsil_stdout.cpp`

9.80 VSIStdoutHandle Class Reference

Inheritance diagram for VSIStdoutHandle:




The documentation for this class was generated from the following file:

- cpl_vsil_stdout.cpp

9.81 VSIStdoutRedirectFilesystemHandler Class Reference

Inheritance diagram for VSIStdoutRedirectFilesystemHandler:




The documentation for this class was generated from the following file:

- cpl_vsil_stdout.cpp

9.82 VSIStdoutRedirectHandle Class Reference

Inheritance diagram for VSIStdoutRedirectHandle:




The documentation for this class was generated from the following file:

- cpl_vsil_stdout.cpp

9.83 VSISubFileFilesystemHandler Class Reference

Inheritance diagram for VSISubFileFilesystemHandler:




The documentation for this class was generated from the following file:

- cpl_vsil_subfile.cpp

9.84 VSISubFileHandle Class Reference

Inheritance diagram for VSISubFileHandle:




The documentation for this class was generated from the following file:

- `cpl_vsil_subfile.cpp`

9.85 VSITarEntryFileOffset Class Reference

Inheritance diagram for VSITarEntryFileOffset:




The documentation for this class was generated from the following file:

- `cpl_vsil_tar.cpp`

9.86 VSITarFilesystemHandler Class Reference

Inheritance diagram for VSITarFilesystemHandler:




The documentation for this class was generated from the following file:

- `cpl_vsil_tar.cpp`

9.87 VSITarReader Class Reference

Inheritance diagram for VSITarReader:




The documentation for this class was generated from the following file:

- `cpl_vsil_tar.cpp`

9.88 VSIUnixStdioFilesystemHandler Class Reference

Inheritance diagram for VSIUnixStdioFilesystemHandler:




The documentation for this class was generated from the following file:

- `cpl_vsil_unix_stdio_64.cpp`

9.89 VSIUnixStdioHandle Class Reference

Inheritance diagram for VSIUnixStdioHandle:




The documentation for this class was generated from the following file:

- `cpl_vsil_unix_stdio_64.cpp`

9.90 VSIVirtualHandle Class Reference

Inheritance diagram for VSIVirtualHandle:




The documentation for this class was generated from the following files:

- `cpl_vsi_virtual.h`
- `cpl_vsil.cpp`

9.91 VSIZipEntryFileOffset Class Reference

Inheritance diagram for VSIZipEntryFileOffset:




The documentation for this class was generated from the following file:

- `cpl_vsil_gzip.cpp`

9.92 VSIZipFilesystemHandler Class Reference

Inheritance diagram for VSIZipFilesystemHandler:




The documentation for this class was generated from the following file:

- `cpl_vsil_gzip.cpp`

9.93 VSIZipReader Class Reference

Inheritance diagram for VSIZipReader:




The documentation for this class was generated from the following file:

- `cpl_vsil_gzip.cpp`

9.94 VSIZipWriteHandle Class Reference

Inheritance diagram for VSIZipWriteHandle:



The documentation for this class was generated from the following file:

- `cpl_vsil_gzip.cpp`

9.95 zip_fileinfo Struct Reference

The documentation for this struct was generated from the following file:

- `cpl_minizip_zip.h`

9.96 zip_internal Struct Reference

The documentation for this struct was generated from the following file:

- cpl_minizip_zip.cpp

9.97 zlib_filefunc_def_s Struct Reference

The documentation for this struct was generated from the following file:

- cpl_minizip_ioapi.h

Chapter 10

File Documentation

10.1 cpl_conv.h File Reference

```
#include "cpl_port.h"
#include "cpl_vsip.h"
#include "cpl_error.h"
```

Classes

- struct [CPLSharedFileInfo](#)

Functions

- const char CPL_DLL *[CPL_STDCALL CPLGetConfigOption](#) (const char *, const char *) CPL_WARN_UNUSED_RESULT
- void CPL_DLL CPL_STDCALL [CPLSetConfigOption](#) (const char *, const char *)
- void CPL_DLL CPL_STDCALL [CPLSetThreadLocalConfigOption](#) (const char *pszKey, const char *pszValue)
- void CPL_DLL *[CPLMalloc](#) (size_t) CPL_WARN_UNUSED_RESULT
- void CPL_DLL *[CPLCalloc](#) (size_t, size_t) CPL_WARN_UNUSED_RESULT
- void CPL_DLL *[CPLRealloc](#) (void *, size_t) CPL_WARN_UNUSED_RESULT
- char CPL_DLL *[CPLStrdup](#) (const char *) CPL_WARN_UNUSED_RESULT
- char CPL_DLL *[CPLStrlwr](#) (char *)
- char CPL_DLL *[CPLFGets](#) (char *, int, FILE *)
- const char CPL_DLL *[CPLReadLine](#) (FILE *)
- const char CPL_DLL *[CPLReadLineL](#) (VSILFILE *)
- const char CPL_DLL *[CPLReadLine2L](#) (VSILFILE *, int nMaxCols, char **papszOptions)
- double CPL_DLL [CPLAtof](#) (const char *)
- double CPL_DLL [CPLAtofDelim](#) (const char *, char)
- double CPL_DLL [CPLStrtod](#) (const char *, char **)
- double CPL_DLL [CPLStrtodDelim](#) (const char *, char **, char)
- float CPL_DLL [CPLStrtof](#) (const char *, char **)
- float CPL_DLL [CPLStrtofDelim](#) (const char *, char **, char)
- double CPL_DLL [CPLAtofM](#) (const char *)
- char CPL_DLL *[CPLScanString](#) (const char *, int, int, int)
- double CPL_DLL [CPLScanDouble](#) (const char *, int)
- long CPL_DLL [CPLScanLong](#) (const char *, int)
- unsigned long CPL_DLL [CPLScanULong](#) (const char *, int)
- GUIntBig CPL_DLL [CPLScanUIntBig](#) (const char *, int)

- void CPL_DLL * [CPLScanPointer](#) (const char *, int)
- int CPL_DLL [CPLPrintString](#) (char *, const char *, int)
- int CPL_DLL [CPLPrintStringFill](#) (char *, const char *, int)
- int CPL_DLL [CPLPrintInt32](#) (char *, GLint32, int)
- int CPL_DLL [CPLPrintULintBig](#) (char *, GLuintBig, int)
- int CPL_DLL [CPLPrintDouble](#) (char *, const char *, double, const char *)
- int CPL_DLL [CPLPrintTime](#) (char *, int, const char *, const struct tm *, const char *)
- int CPL_DLL [CPLPrintPointer](#) (char *, void *, int)
- void CPL_DLL * [CPLGetSymbol](#) (const char *, const char *)
- int CPL_DLL [CPLGetExecPath](#) (char *pszPathBuf, int nMaxLength)
- const char CPL_DLL * [CPLGetPath](#) (const char *)
- const char CPL_DLL * [CPLGetDirname](#) (const char *)
- const char CPL_DLL * [CPLGetFilename](#) (const char *)
- const char CPL_DLL * [CPLGetBasename](#) (const char *)
- const char CPL_DLL * [CPLGetExtension](#) (const char *)
- char CPL_DLL * [CPLGetCurrentDir](#) (void)
- const char CPL_DLL * [CPLFormFilename](#) (const char *pszPath, const char *pszBasename, const char *pszExtension)
- const char CPL_DLL * [CPLFormClFilename](#) (const char *pszPath, const char *pszBasename, const char *pszExtension)
- const char CPL_DLL * [CPLResetExtension](#) (const char *, const char *)
- const char CPL_DLL * [CPLProjectRelativeFilename](#) (const char *pszProjectDir, const char *pszSecondaryFilename)
- int CPL_DLL [CPLIsFilenameRelative](#) (const char *pszFilename)
- const char CPL_DLL * [CPLExtractRelativePath](#) (const char *, const char *, int *)
- const char CPL_DLL * [CPLCleanTrailingSlash](#) (const char *)
- char CPL_DLL ** [CPLCorrespondingPaths](#) (const char *pszOldFilename, const char *pszNewFilename, char **papszFileList)
- int CPL_DLL [CPLCheckForFile](#) (char *pszFilename, char **papszSiblingList)
- const char CPL_DLL * [CPLGenerateTempFilename](#) (const char *pszStem)
- FILE CPL_DLL * [CPLOpenShared](#) (const char *, const char *, int)
- void CPL_DLL [CPLCloseShared](#) (FILE *)
- [CPLSharedFileInfo](#) CPL_DLL * [CPLGetSharedList](#) (int *)
- void CPL_DLL [CPLDumpSharedList](#) (FILE *)
- double CPL_DLL [CPLPackedDMSToDec](#) (double)
- double CPL_DLL [CPLDecToPackedDMS](#) (double dfDec)
- int CPL_DLL [CPLUnlinkTree](#) (const char *)

10.1.1 Detailed Description

Various convenience functions for CPL.

10.1.2 Function Documentation

10.1.2.1 double CPL_DLL CPLAtof (const char * *nptr*)

Converts ASCII string to floating point number.

This function converts the initial portion of the string pointed to by *nptr* to double floating point representation. The behaviour is the same as

```
CPLStrtod(nptr, (char **)NULL);
```

This function does the same as standard `atof(3)`, but does not take locale in account. That means, the decimal delimiter is always '.' (decimal point). Use [CPLAtofDelim\(\)](#) function if you want to specify custom delimiter.

IMPORTANT NOTE. Existence of this function does not mean you should always use it. Sometimes you should use standard locale aware `atof(3)` and its family. When you need to process the user's input (for example, command line parameters) use `atof(3)`, because user works in localized environment and her input will be done accordingly the locale set. In particular that means we should not make assumptions about character used as decimal delimiter, it can be either `"."` or `,`. But when you are parsing some ASCII file in predefined format, you most likely need [CPLAtof\(\)](#), because such files distributed across the systems with different locales and floating point representation should be considered as a part of file format. If the format uses `"."` as a delimiter the same character must be used when parsing number regardless of actual locale setting.

Parameters

<i>nptr</i>	Pointer to string to convert.
-------------	-------------------------------

Returns

Converted value, if any.

10.1.2.2 double CPL_DLL CPLAtofDelim (const char * *nptr*, char *point*)

Converts ASCII string to floating point number.

This function converts the initial portion of the string pointed to by *nptr* to double floating point representation. The behaviour is the same as

```
CPLStrtodDelim(nptr, (char **)NULL, point);
```

This function does the same as standard `atof(3)`, but does not take locale in account. Instead of locale defined decimal delimiter you can specify your own one. Also see notes for [CPLAtof\(\)](#) function.

Parameters

<i>nptr</i>	Pointer to string to convert.
<i>point</i>	Decimal delimiter.

Returns

Converted value, if any.

10.1.2.3 double CPL_DLL CPLAtofM (const char * *nptr*)

Converts ASCII string to floating point number using any numeric locale.

This function converts the initial portion of the string pointed to by *nptr* to double floating point representation. This function does the same as standard `atof()`, but it allows a variety of locale representations. That is it supports numeric values with either a comma or a period for the decimal delimiter.

PS. The M stands for Multi-lingual.

Parameters

<i>nptr</i>	The string to convert.
-------------	------------------------

Returns

Converted value, if any. Zero on failure.

10.1.2.4 void CPL_DLL* CPLCalloc (size_t nCount, size_t nSize)

Safe version of calloc().

This function is like the C library calloc(), but raises a CE_Fatal error with CPLError() if it fails to allocate the desired memory. It should be used for small memory allocations that are unlikely to fail and for which the application is unwilling to test for out of memory conditions. It uses VSICalloc() to get the memory, so any hooking of VSICalloc() will apply to [CPLCalloc\(\)](#) as well. CPLFree() or VSIFree() can be used free memory allocated by [CPLCalloc\(\)](#).

Parameters

<i>nCount</i>	number of objects to allocate.
<i>nSize</i>	size (in bytes) of object to allocate.

Returns

pointer to newly allocated memory, only NULL if nSize * nCount is NULL.

10.1.2.5 int CPL_DLL CPLCheckForFile (char * pszFilename, char ** papszSiblingFiles)

Check for file existance.

The function checks if a named file exists in the filesystem, hopefully in an efficient fashion if a sibling file list is available. It exists primarily to do faster file checking for functions like GDAL open methods that get a list of files from the target directory.

If the sibling file list exists (is not NULL) it is assumed to be a list of files in the same directory as the target file, and it will be checked (case insensitively) for a match. If a match is found, pszFilename is updated with the correct case and TRUE is returned.

If papszSiblingFiles is NULL, a [VSIStatL\(\)](#) is used to test for the files existance, and no case insensitive testing is done.

Parameters

<i>pszFilename</i>	name of file to check for - filename case updated in some cases.
<i>papszSibling-Files</i>	a list of files in the same directory as pszFilename if available, or NULL. This list should have no path components.

Returns

TRUE if a match is found, or FALSE if not.

10.1.2.6 const char CPL_DLL* CPLCleanTrailingSlash (const char * pszPath)

Remove trailing forward/backward slash from the path for unix/windows resp.

Returns a string containing the portion of the passed path string with trailing slash removed. If there is no path in the passed filename an empty string will be returned (not NULL).

```
CPLCleanTrailingSlash( "abc/def/" ) == "abc/def"
CPLCleanTrailingSlash( "abc/def" ) == "abc/def"
CPLCleanTrailingSlash( "c:\\abc\\def\\" ) == "c:\\abc\\def"
CPLCleanTrailingSlash( "c:\\abc\\def" ) == "c:\\abc\\def"
CPLCleanTrailingSlash( "abc" ) == "abc"
```

Parameters

<i>pszPath</i>	the path to be cleaned up
----------------	---------------------------

Returns

Path in an internal string which must not be freed. The string may be destroyed by the next CPL filename handling call.

10.1.2.7 void CPL_DLL CPLCloseShared (FILE * fp)

Close shared file.

Dereferences the indicated file handle, and closes it if the reference count has dropped to zero. A CPLError() is issued if the file is not in the shared file list.

Parameters

<i>fp</i>	file handle from CPLOpenShared() to deaccess.
-----------	---

10.1.2.8 char CPL_DLL CPLCorrespondingPaths (const char * pszOldFilename, const char * pszNewFilename, char ** ppszFileList)**

Identify corresponding paths.

Given a prototype old and new filename this function will attempt to determine corresponding names for a set of other old filenames that will rename them in a similar manner. This correspondance assumes there are two possibly kinds of renaming going on. A change of path, and a change of filename stem.

If a consistent renaming cannot be established for all the files this function will return indicating an error.

The returned file list becomes owned by the caller and should be destroyed with [CSLDestroy\(\)](#).

Parameters

<i>pszOldFilename</i>	path to old prototype file.
<i>pszNew-Filename</i>	path to new prototype file.
<i>ppszFileList</i>	list of other files associated with <i>pszOldFilename</i> to rename similarly.

Returns

a list of files corresponding to *ppszFileList* but renamed to correspond to *pszNewFilename*.

10.1.2.9 double CPL_DLL CPLDecToPackedDMS (double dfDec)

Convert decimal degrees into packed DMS value (DDDDMMSSS.SS).

This function converts a value, specified in decimal degrees into packed DMS angle. The standard packed DMS format is:

degrees * 1000000 + minutes * 1000 + seconds

See also [CPLPackedDMSToDec\(\)](#).

Parameters

<i>dfDec</i>	Angle in decimal degrees.
--------------	---------------------------

Returns

Angle in packed DMS format.

10.1.2.10 void CPL_DLL CPLDumpSharedList (FILE * *fp*)

Report open shared files.

Dumps all open shared files to the indicated file handle. If the file handle is NULL information is sent via the CPLDebug() call.

Parameters

<i>fp</i>	File handle to write to.
-----------	--------------------------

10.1.2.11 const char CPL_DLL* CPLExtractRelativePath (const char * *pszBaseDir*, const char * *pszTarget*, int * *pbGotRelative*)

Get relative path from directory to target file.

Computes a relative path for *pszTarget* relative to *pszBaseDir*. Currently this only works if they share a common base path. The returned path is normally into the *pszTarget* string. It should only be considered valid as long as *pszTarget* is valid or till the next call to this function, whichever comes first.

Parameters

<i>pszBaseDir</i>	the name of the directory relative to which the path should be computed. <i>pszBaseDir</i> may be NULL in which case the original target is returned without relativizing.
<i>pszTarget</i>	the filename to be changed to be relative to <i>pszBaseDir</i> .
<i>pbGotRelative</i>	Pointer to location in which a flag is placed indicating that the returned path is relative to the basename (TRUE) or not (FALSE). This pointer may be NULL if flag is not desired.

Returns

an adjusted path or the original if it could not be made relative to the *pszBaseFile*'s path.

10.1.2.12 char CPL_DLL* CPLFGets (char * *pszBuffer*, int *nBufferSize*, FILE * *fp*)

Reads in at most one less than *nBufferSize* characters from the *fp* stream and stores them into the buffer pointed to by *pszBuffer*. Reading stops after an EOF or a newline. If a newline is read, it is *not* stored into the buffer. A '\0' is stored after the last character in the buffer. All three types of newline terminators recognized by the [CPLFGets\(\)](#): single '\r' and '\n' and '\r\n' combination.

Parameters

<i>pszBuffer</i>	pointer to the targeting character buffer.
<i>nBufferSize</i>	maximum size of the string to read (not including terminating '\0').
<i>fp</i>	file pointer to read from.

Returns

pointer to the *pszBuffer* containing a string read from the file or NULL if the error or end of file was encountered.

10.1.2.13 const char CPL_DLL* CPLFormCIFilename (const char * *pszPath*, const char * *pszBasename*, const char * *pszExtension*)

Case insensitive file searching, returning full path.

This function tries to return the path to a file regardless of whether the file exactly matches the basename, and extension case, or is all upper case, or all lower case. The path is treated as case sensitive. This function is equivalent to [CPLFormFilename\(\)](#) on case insensitive file systems (like Windows).

Parameters

<i>pszPath</i>	directory path to the directory containing the file. This may be relative or absolute, and may have a trailing path separator or not. May be NULL.
<i>pszBasename</i>	file basename. May optionally have path and/or extension. May not be NULL.
<i>pszExtension</i>	file extension, optionally including the period. May be NULL.

Returns

a fully formed filename in an internal static string. Do not modify or free the returned string. The string may be destroyed by the next CPL call.

10.1.2.14 const char CPL_DLL* CPLFormFilename (const char * *pszPath*, const char * *pszBasename*, const char * *pszExtension*)

Build a full file path from a passed path, file basename and extension.

The path, and extension are optional. The basename may in fact contain an extension if desired.

```
CPLFormFilename ("abc/xyz","def", ".dat" ) == "abc/xyz/def.dat"
CPLFormFilename (NULL,"def", NULL ) == "def"
CPLFormFilename (NULL,"abc/def.dat", NULL ) == "abc/def.dat"
CPLFormFilename ("/abc/xyz/","def.dat", NULL ) == "/abc/xyz/def.dat"
```

Parameters

<i>pszPath</i>	directory path to the directory containing the file. This may be relative or absolute, and may have a trailing path separator or not. May be NULL.
<i>pszBasename</i>	file basename. May optionally have path and/or extension. May not be NULL.
<i>pszExtension</i>	file extension, optionally including the period. May be NULL.

Returns

a fully formed filename in an internal static string. Do not modify or free the returned string. The string may be destroyed by the next CPL call.

10.1.2.15 const char CPL_DLL* CPLGenerateTempFilename (const char * *pszStem*)

Generate temporary file name.

Returns a filename that may be used for a temporary file. The location of the file tries to follow operating system semantics but may be forced via the CPL_TMPDIR configuration option.

Parameters

<i>pszStem</i>	if non-NULL this will be part of the filename.
----------------	--

Returns

a filename which is valid till the next CPL call in this thread.

10.1.2.16 const char CPL_DLL* CPLGetBasename (const char * *pszFullFilename*)

Extract basename (non-directory, non-extension) portion of filename.

Returns a string containing the file basename portion of the passed name. If there is no basename (passed value ends in trailing directory separator, or filename starts with a dot) an empty string is returned.

```
CPLGetBasename( "abc/def.xyz" ) == "def"
CPLGetBasename( "abc/def" ) == "def"
CPLGetBasename( "abc/def/" ) == ""
```

Parameters

<i>pszFullFilename</i>	the full filename potentially including a path.
------------------------	---

Returns

just the non-directory, non-extension portion of the path in an internal string which must not be freed. The string may be destroyed by the next CPL filename handling call.

10.1.2.17 const char CPL_DLL* CPL_STDCALL CPLGetConfigOption (const char * *pszKey*, const char * *pszDefault*)

Get the value of a configuration option.

The value is the value of a (key, value) option set with [CPLSetConfigOption\(\)](#). If the given option was not defined with [CPLSetConfigOption\(\)](#), it tries to find it in environment variables.

Parameters

<i>pszKey</i>	the key of the option to retrieve
<i>pszDefault</i>	a default value if the key does not match existing defined options (may be NULL)

Returns

the value associated to the key, or the default value if not found

See Also

[CPLSetConfigOption\(\)](#), <http://trac.osgeo.org/gdal/wiki/ConfigOptions>

10.1.2.18 char CPL_DLL* CPLGetCurrentDir (void)

Get the current working directory name.

Returns

a pointer to buffer, containing current working directory path or NULL in case of error. User is responsible to free that buffer after usage with CPLFree() function. If HAVE_GETCWD macro is not defined, the function returns NULL.

10.1.2.19 const char CPL_DLL* CPLGetDirname (const char * *pszFilename*)

Extract directory path portion of filename.

Returns a string containing the directory path portion of the passed filename. If there is no path in the passed filename the dot will be returned. It is the only difference from [CPLGetPath\(\)](#).

```
CPLGetDirname( "abc/def.xyz" ) == "abc"
```

```
CPLGetDirname( "/abc/def/" ) == "/abc/def"
CPLGetDirname( "/" ) == "/"
CPLGetDirname( "/abc/def" ) == "/abc"
CPLGetDirname( "abc" ) == ". "
```

Parameters

<i>pszFilename</i>	the filename potentially including a path.
--------------------	--

Returns

Path in an internal string which must not be freed. The string may be destroyed by the next CPL filename handling call. The returned will generally not contain a trailing path separator.

10.1.2.20 int CPL_DLL CPLGetExecPath (char * *pszPathBuf*, int *nMaxLength*)

Fetch path of executable.

The path to the executable currently running is returned. This path includes the name of the executable. Currently this only works on win32 and linux platforms. The returned path is UTF-8 encoded.

Parameters

<i>pszPathBuf</i>	the buffer into which the path is placed.
<i>nMaxLength</i>	the buffer size, MAX_PATH+1 is suggested.

Returns

FALSE on failure or TRUE on success.

10.1.2.21 const char CPL_DLL* CPLGetExtension (const char * *pszFullFilename*)

Extract filename extension from full filename.

Returns a string containing the extention portion of the passed name. If there is no extension (the filename has no dot) an empty string is returned. The returned extension will not include the period.

```
CPLGetExtension( "abc/def.xyz" ) == "xyz"
CPLGetExtension( "abc/def" ) == ""
```

Parameters

<i>pszFullFilename</i>	the full filename potentially including a path.
------------------------	---

Returns

just the extension portion of the path in an internal string which must not be freed. The string may be destroyed by the next CPL filename handling call.

10.1.2.22 const char CPL_DLL* CPLGetFilename (const char * *pszFullFilename*)

Extract non-directory portion of filename.

Returns a string containing the bare filename portion of the passed filename. If there is no filename (passed value ends in trailing directory separator) an empty string is returned.

```
CPLGetFilename( "abc/def.xyz" ) == "def.xyz"
CPLGetFilename( "/abc/def/" ) == ""
CPLGetFilename( "abc/def" ) == "def"
```

Parameters

<i>pszFullFilename</i>	the full filename potentially including a path.
------------------------	---

Returns

just the non-directory portion of the path (points back into original string).

10.1.2.23 const char CPL_DLL* CPLGetPath (const char * *pszFilename*)

Extract directory path portion of filename.

Returns a string containing the directory path portion of the passed filename. If there is no path in the passed filename an empty string will be returned (not NULL).

```
CPLGetPath( "abc/def.xyz" ) == "abc"
CPLGetPath( "/abc/def/" ) == "/abc/def"
CPLGetPath( "/" ) == "/"
CPLGetPath( "/abc/def" ) == "/abc"
CPLGetPath( "abc" ) == ""
```

Parameters

<i>pszFilename</i>	the filename potentially including a path.
--------------------	--

Returns

Path in an internal string which must not be freed. The string may be destroyed by the next CPL filename handling call. The returned will generally not contain a trailing path separator.

10.1.2.24 CPLSharedFileInfo CPL_DLL* CPLGetSharedList (int * *pnCount*)

Fetch list of open shared files.

Parameters

<i>pnCount</i>	place to put the count of entries.
----------------	------------------------------------

Returns

the pointer to the first in the array of shared file info structures.

10.1.2.25 void CPL_DLL* CPLGetSymbol (const char * *pszLibrary*, const char * *pszSymbolName*)

Fetch a function pointer from a shared library / DLL.

This function is meant to abstract access to shared libraries and DLLs and performs functions similar to `dlopen()`/`dlsym()` on Unix and `LoadLibrary()` / `GetProcAddress()` on Windows.

If no support for loading entry points from a shared library is available this function will always return NULL. Rules on when this function issues a `CPLError()` or not are not currently well defined, and will have to be resolved in the

future.

Currently [CPLGetSymbol\(\)](#) doesn't try to:

- prevent the reference count on the library from going up for every request, or given any opportunity to unload the library.
- Attempt to look for the library in non-standard locations.
- Attempt to try variations on the symbol name, like pre-pending or post-pending an underscore.

Some of these issues may be worked on in the future.

Parameters

<i>pszLibrary</i>	the name of the shared library or DLL containing the function. May contain path to file. If not system supplies search paths will be used.
<i>pszSymbolName</i>	the name of the function to fetch a pointer to.

Returns

A pointer to the function if found, or NULL if the function isn't found, or the shared library can't be loaded.

10.1.2.26 int CPL_DLL CPLIsFilenameRelative (const char * *pszFilename*)

Is filename relative or absolute?

The test is filesystem convention agnostic. That is it will test for Unix style and windows style path conventions regardless of the actual system in use.

Parameters

<i>pszFilename</i>	the filename with path to test.
--------------------	---------------------------------

Returns

TRUE if the filename is relative or FALSE if it is absolute.

10.1.2.27 void CPL_DLL* CPLMalloc (size_t *nSize*)

Safe version of malloc().

This function is like the C library malloc(), but raises a CE_Fatal error with CPLError() if it fails to allocate the desired memory. It should be used for small memory allocations that are unlikely to fail and for which the application is unwilling to test for out of memory conditions. It uses VSIMalloc() to get the memory, so any hooking of VSIMalloc() will apply to [CPLMalloc\(\)](#) as well. CPLFree() or VSIFree() can be used free memory allocated by [CPLMalloc\(\)](#).

Parameters

<i>nSize</i>	size (in bytes) of memory block to allocate.
--------------	--

Returns

pointer to newly allocated memory, only NULL if nSize is zero.

10.1.2.28 FILE CPL_DLL* CPLOpenShared (const char * pszFilename, const char * pszAccess, int bLarge)

Open a shared file handle.

Some operating systems have limits on the number of file handles that can be open at one time. This function attempts to maintain a registry of already open file handles, and reuse existing ones if the same file is requested by another part of the application.

Note that access is only shared for access types "r", "rb", "r+" and "rb+". All others will just result in direct VSIOpen() calls. Keep in mind that a file is only reused if the file name is exactly the same. Different names referring to the same file will result in different handles.

The VSIFOpen() or [VSIFOpenL\(\)](#) function is used to actually open the file, when an existing file handle can't be shared.

Parameters

<i>pszFilename</i>	the name of the file to open.
<i>pszAccess</i>	the normal fopen()/VSIFOpen() style access string.
<i>bLarge</i>	If TRUE VSIFOpenL() (for large files) will be used instead of VSIFOpen().

Returns

a file handle or NULL if opening fails.

10.1.2.29 double CPL_DLL CPLPackedDMSToDec (double dfPacked)

Convert a packed DMS value (DDDDMMSSS.SS) into decimal degrees.

This function converts a packed DMS angle to seconds. The standard packed DMS format is:

degrees * 1000000 + minutes * 1000 + seconds

Example: ang = 120025045.25 yields deg = 120 min = 25 sec = 45.25

The algorithm used for the conversion is as follows:

1. The absolute value of the angle is used.
1. The degrees are separated out: deg = ang/1000000 (fractional portion truncated)
1. The minutes are separated out: min = (ang - deg * 1000000) / 1000 (fractional portion truncated)
1. The seconds are then computed: sec = ang - deg * 1000000 - min * 1000
1. The total angle in seconds is computed: sec = deg * 3600.0 + min * 60.0 + sec
1. The sign of sec is set to that of the input angle.

Packed DMS values used by the USGS GCTP package and probably by other software.

NOTE: This code does not validate input value. If you give the wrong value, you will get the wrong result.

Parameters

<i>dfPacked</i>	Angle in packed DMS format.
-----------------	-----------------------------

Returns

Angle in decimal degrees.

10.1.2.30 int CPL_DLL CPLPrintDouble (char * *pszBuffer*, const char * *pszFormat*, double *dfValue*, const char * *pszLocale*)

Print double value into specified string buffer. Exponential character flag 'E' (or 'e') will be replaced with 'D', as in Fortran. Resulting string will not be NULL-terminated.

Parameters

<i>pszBuffer</i>	Pointer to the destination string buffer. Should be large enough to hold the resulting string. Note, that the string will not be NULL-terminated, so user should do this himself, if needed.
<i>pszFormat</i>	Format specifier (for example, "%16.9E").
<i>dfValue</i>	Numerical value to print.
<i>pszLocale</i>	Pointer to a character string containing locale name ("C", "POSIX", "us_US", "ru_RU.KOI8-R" etc.). If NULL we will not manipulate with locale settings and current process locale will be used for printing. With the pszLocale option we can control what exact locale will be used for printing a numeric value to the string (in most cases it should be C/POSIX).

Returns

Number of characters printed.

10.1.2.31 int CPL_DLL CPLPrintInt32 (char * *pszBuffer*, GLint32 *iValue*, int *nMaxLen*)

Print GLint32 value into specified string buffer. This string will not be NULL-terminated.

Parameters

<i>pszBuffer</i>	Pointer to the destination string buffer. Should be large enough to hold the resulting string. Note, that the string will not be NULL-terminated, so user should do this himself, if needed.
<i>iValue</i>	Numerical value to print.
<i>nMaxLen</i>	Maximum length of the resulting string. If string length is greater than nMaxLen, it will be truncated.

Returns

Number of characters printed.

10.1.2.32 int CPL_DLL CPLPrintPointer (char * *pszBuffer*, void * *pValue*, int *nMaxLen*)

Print pointer value into specified string buffer. This string will not be NULL-terminated.

Parameters

<i>pszBuffer</i>	Pointer to the destination string buffer. Should be large enough to hold the resulting string. Note, that the string will not be NULL-terminated, so user should do this himself, if needed.
<i>pValue</i>	Pointer to ASCII encode.
<i>nMaxLen</i>	Maximum length of the resulting string. If string length is greater than nMaxLen, it will be truncated.

Returns

Number of characters printed.

10.1.2.33 int CPL_DLL CPLPrintString (*char * pszDest, const char * pszSrc, int nMaxLen*)

Copy the string pointed to by pszSrc, NOT including the terminating '\0' character, to the array pointed to by pszDest.

Parameters

<i>pszDest</i>	Pointer to the destination string buffer. Should be large enough to hold the resulting string.
<i>pszSrc</i>	Pointer to the source buffer.
<i>nMaxLen</i>	Maximum length of the resulting string. If string length is greater than nMaxLen, it will be truncated.

Returns

Number of characters printed.

10.1.2.34 int CPL_DLL CPLPrintStringFill (*char * pszDest, const char * pszSrc, int nMaxLen*)

Copy the string pointed to by pszSrc, NOT including the terminating '\0' character, to the array pointed to by pszDest. Remainder of the destination string will be filled with space characters. This is only difference from the PrintString().

Parameters

<i>pszDest</i>	Pointer to the destination string buffer. Should be large enough to hold the resulting string.
<i>pszSrc</i>	Pointer to the source buffer.
<i>nMaxLen</i>	Maximum length of the resulting string. If string length is greater than nMaxLen, it will be truncated.

Returns

Number of characters printed.

10.1.2.35 int CPL_DLL CPLPrintTime (*char * pszBuffer, int nMaxLen, const char * pszFormat, const struct tm * poBrokenTime, const char * pszLocale*)

Print specified time value accordingly to the format options and specified locale name. This function does following:

- if locale parameter is not NULL, the current locale setting will be stored and replaced with the specified one;
- format time value with the strftime(3) function;
- restore back current locale, if was saved.

Parameters

<i>pszBuffer</i>	Pointer to the destination string buffer. Should be large enough to hold the resulting string. Note, that the string will not be NULL-terminated, so user should do this himself, if needed.
<i>nMaxLen</i>	Maximum length of the resulting string. If string length is greater than nMaxLen, it will be truncated.
<i>pszFormat</i>	Controls the output format. Options are the same as for strftime(3) function.
<i>poBrokenTime</i>	Pointer to the broken-down time structure. May be requested with the VSIGMTIME() and VSI-LocalTime() functions.

<i>pszLocale</i>	Pointer to a character string containing locale name ("C", "POSIX", "us_US", "ru_RU.KOI8-R" etc.). If NULL we will not manipulate with locale settings and current process locale will be used for printing. Be aware that it may be unsuitable to use current locale for printing time, because all names will be printed in your native language, as well as time format settings also may be adjusted differently from the C/POSIX defaults. To solve these problems this option was introduced.
------------------	---

Returns

Number of characters printed.

10.1.2.36 int CPL_DLL CPLPrintUIntBig (char * *pszBuffer*, GUIIntBig *iValue*, int *nMaxLen*)

Print GUIIntBig value into specified string buffer. This string will not be NULL-terminated.

Parameters

<i>pszBuffer</i>	Pointer to the destination string buffer. Should be large enough to hold the resulting string. Note, that the string will not be NULL-terminated, so user should do this himself, if needed.
<i>iValue</i>	Numerical value to print.
<i>nMaxLen</i>	Maximum length of the resulting string. If string length is greater than nMaxLen, it will be truncated.

Returns

Number of characters printed.

10.1.2.37 const char CPL_DLL* CPLProjectRelativeFilename (const char * *pszProjectDir*, const char * *pszSecondaryFilename*)

Find a file relative to a project file.

Given the path to a "project" directory, and a path to a secondary file referenced from that project, build a path to the secondary file that the current application can use. If the secondary path is already absolute, rather than relative, then it will be returned unaltered.

Examples:

```
CPLProjectRelativeFilename("abc/def", "tmp/abc.gif") == "abc/def/tmp/abc.gif"
CPLProjectRelativeFilename("abc/def", "/tmp/abc.gif") == "/tmp/abc.gif"
CPLProjectRelativeFilename("/xy", "abc.gif") == "/xy/abc.gif"
CPLProjectRelativeFilename("/abc/def", "../abc.gif") == "/abc/def/..../abc.gif"
CPLProjectRelativeFilename("C:\WIN", "abc.gif") == "C:\WIN\abc.gif"
```

Parameters

<i>pszProjectDir</i>	the directory relative to which the secondary files path should be interpreted.
<i>pszSecondary-Filename</i>	the filename (potentially with path) that is to be interpreted relative to the project directory.

Returns

a composed path to the secondary file. The returned string is internal and should not be altered, freed, or depending on past the next CPL call.

10.1.2.38 const char CPL_DLL* CPLReadLine(FILE * fp)

Simplified line reading from text file.

Read a line of text from the given file handle, taking care to capture CR and/or LF and strip off ... equivalent of DKReadLine(). Pointer to an internal buffer is returned. The application shouldn't free it, or depend on its value past the next call to [CPLReadLine\(\)](#).

Note that [CPLReadLine\(\)](#) uses VSIFGets(), so any hooking of VSI file services should apply to [CPLReadLine\(\)](#) as well.

[CPLReadLine\(\)](#) maintains an internal buffer, which will appear as a single block memory leak in some circumstances. [CPLReadLine\(\)](#) may be called with a NULL FILE * at any time to free this working buffer.

Parameters

<i>fp</i>	file pointer opened with VSIFOpen().
-----------	--------------------------------------

Returns

pointer to an internal buffer containing a line of text read from the file or NULL if the end of file was encountered.

10.1.2.39 const char CPL_DLL* CPLReadLine2L(VSILFILE * fp, int nMaxCars, char ** papszOptions)

Simplified line reading from text file.

Similar to [CPLReadLine\(\)](#), but reading from a large file API handle.

Parameters

<i>fp</i>	file pointer opened with VSIFOpenL() .
<i>nMaxCars</i>	maximum number of characters allowed, or -1 for no limit.
<i>papszOptions</i>	NULL-terminated array of options. Unused for now.

Returns

pointer to an internal buffer containing a line of text read from the file or NULL if the end of file was encountered or the maximum number of characters allowed reached.

Since

GDAL 1.7.0

10.1.2.40 const char CPL_DLL* CPLReadLineL(VSILFILE * fp)

Simplified line reading from text file.

Similar to [CPLReadLine\(\)](#), but reading from a large file API handle.

Parameters

<i>fp</i>	file pointer opened with VSIFOpenL() .
-----------	--

Returns

pointer to an internal buffer containing a line of text read from the file or NULL if the end of file was encountered.

10.1.2.41 void CPL_DLL* CPLRealloc (void * *pData*, size_t *nNewSize*)

Safe version of realloc().

This function is like the C library realloc(), but raises a CE_Fatal error with CPLError() if it fails to allocate the desired memory. It should be used for small memory allocations that are unlikely to fail and for which the application is unwilling to test for out of memory conditions. It uses VSIRealloc() to get the memory, so any hooking of VSIRealloc() will apply to [CPLRealloc\(\)](#) as well. CPLFree() or VSIFree() can be used free memory allocated by [CPLRealloc\(\)](#).

It is also safe to pass NULL in as the existing memory block for [CPLRealloc\(\)](#), in which case it uses VSIMalloc() to allocate a new block.

Parameters

<i>pData</i>	existing memory block which should be copied to the new block.
<i>nNewSize</i>	new size (in bytes) of memory block to allocate.

Returns

pointer to allocated memory, only NULL if nNewSize is zero.

10.1.2.42 const char CPL_DLL* CPLResetExtension (const char * *pszPath*, const char * *pszExt*)

Replace the extension with the provided one.

Parameters

<i>pszPath</i>	the input path, this string is not altered.
<i>pszExt</i>	the new extension to apply to the given path.

Returns

an altered filename with the new extension. Do not modify or free the returned string. The string may be destroyed by the next CPL call.

10.1.2.43 double CPL_DLL CPLScanDouble (const char * *pszString*, int *nMaxLength*)

Extract double from string.

Scan up to a maximum number of characters from a string and convert the result to a double. This function uses [CPLAtof\(\)](#) to convert string to double value, so it uses a comma as a decimal delimiter.

Parameters

<i>pszString</i>	String containing characters to be scanned. It may be terminated with a null character.
<i>nMaxLength</i>	The maximum number of character to consider as part of the number. Less characters will be considered if a null character is encountered.

Returns

Double value, converted from its ASCII form.

10.1.2.44 long CPL_DLL CPLScanLong (const char * *pszString*, int *nMaxLength*)

Scan up to a maximum number of characters from a string and convert the result to a long.

Parameters

<i>pszString</i>	String containing characters to be scanned. It may be terminated with a null character.
<i>nMaxLength</i>	The maximum number of character to consider as part of the number. Less characters will be considered if a null character is encountered.

Returns

Long value, converted from its ASCII form.

10.1.2.45 void CPL_DLL* CPLScanPointer (const char * *pszString*, int *nMaxLength*)

Extract pointer from string.

Scan up to a maximum number of characters from a string and convert the result to a pointer.

Parameters

<i>pszString</i>	String containing characters to be scanned. It may be terminated with a null character.
<i>nMaxLength</i>	The maximum number of character to consider as part of the number. Less characters will be considered if a null character is encountered.

Returns

pointer value, converted from its ASCII form.

10.1.2.46 char CPL_DLL* CPLScanString (const char * *pszString*, int *nMaxLength*, int *bTrimSpaces*, int *bNormalize*)

Scan up to a maximum number of characters from a given string, allocate a buffer for a new string and fill it with scanned characters.

Parameters

<i>pszString</i>	String containing characters to be scanned. It may be terminated with a null character.
<i>nMaxLength</i>	The maximum number of character to read. Less characters will be read if a null character is encountered.
<i>bTrimSpaces</i>	If TRUE, trim ending spaces from the input string. Character considered as empty using isspace(3) function.
<i>bNormalize</i>	If TRUE, replace ':' symbol with the '_'. It is needed if resulting string will be used in CPL dictionaries.

Returns

Pointer to the resulting string buffer. Caller responsible to free this buffer with CPLFree().

10.1.2.47 GUIntBig CPL_DLL CPLScanUIntBig (const char * *pszString*, int *nMaxLength*)

Extract big integer from string.

Scan up to a maximum number of characters from a string and convert the result to a GUIntBig.

Parameters

<i>pszString</i>	String containing characters to be scanned. It may be terminated with a null character.
<i>nMaxLength</i>	The maximum number of character to consider as part of the number. Less characters will be considered if a null character is encountered.

Returns

GUlntBig value, converted from its ASCII form.

10.1.2.48 unsigned long CPL_DLL CPLScanULong (const char * *pszString*, int *nMaxLength*)

Scan up to a maximum number of characters from a string and convert the result to a unsigned long.

Parameters

<i>pszString</i>	String containing characters to be scanned. It may be terminated with a null character.
<i>nMaxLength</i>	The maximum number of character to consider as part of the number. Less characters will be considered if a null character is encountered.

Returns

Unsigned long value, converted from its ASCII form.

10.1.2.49 void CPL_DLL CPL_STDCALL CPLSetConfigOption (const char * *pszKey*, const char * *pszValue*)

Set a configuration option for GDAL/OGR use.

Those options are defined as a (key, value) couple. The value corresponding to a key can be got later with the [CPLGetConfigOption\(\)](#) method.

This mechanism is similar to environment variables, but options set with [CPLSetConfigOption\(\)](#) overrides, for [CPLGetConfigOption\(\)](#) point of view, values defined in the environment.

If [CPLSetConfigOption\(\)](#) is called several times with the same key, the value provided during the last call will be used.

Options can also be passed on the command line of most GDAL utilities with the with '-config KEY VALUE'. For example, ogrinfo --config CPL_DEBUG ON ~/data/test/point.shp

Parameters

<i>pszKey</i>	the key of the option
<i>pszValue</i>	the value of the option, or NULL to clear a setting.

See Also

<http://trac.osgeo.org/gdal/wiki/ConfigOptions>

10.1.2.50 void CPL_DLL CPL_STDCALL CPLSetThreadLocalConfigOption (const char * *pszKey*, const char * *pszValue*)

Set a configuration option for GDAL/OGR use.

Those options are defined as a (key, value) couple. The value corresponding to a key can be got later with the [CPLGetConfigOption\(\)](#) method.

This function sets the configuration option that only applies in the current thread, as opposed to [CPLSetConfigOption\(\)](#) which sets an option that applies on all threads.

Parameters

<i>pszKey</i>	the key of the option
<i>pszValue</i>	the value of the option, or NULL to clear a setting.

10.1.2.51 `char CPL_DLL* CPLStrdup (const char * pszString)`

Safe version of strdup() function.

This function is similar to the C library strdup() function, but if the memory allocation fails it will issue a CE_Fatal error with CPLError() instead of returning NULL. It uses VSIStrdup(), so any hooking of that function will apply to [CPLStrdup\(\)](#) as well. Memory allocated with [CPLStrdup\(\)](#) can be freed with CPLFree() or VSIFree().

It is also safe to pass a NULL string into [CPLStrdup\(\)](#). [CPLStrdup\(\)](#) will allocate and return a zero length string (as opposed to a NULL string).

Parameters

<i>pszString</i>	input string to be duplicated. May be NULL.
------------------	---

Returns

pointer to a newly allocated copy of the string. Free with CPLFree() or VSIFree().

10.1.2.52 `char CPL_DLL* CPLStrlwr (char * pszString)`

Convert each characters of the string to lower case.

For example, "ABcdE" will be converted to "abcde". This function is locale dependent.

Parameters

<i>pszString</i>	input string to be converted.
------------------	-------------------------------

Returns

pointer to the same string, *pszString*.

10.1.2.53 `double CPL_DLL CPLStrtod (const char * nptr, char ** endptr)`

Converts ASCII string to floating point number.

This function converts the initial portion of the string pointed to by *nptr* to double floating point representation. This function does the same as standard strtod(3), but does not take locale in account. That means, the decimal delimiter is always '.' (decimal point). Use [CPLStrtodDelim\(\)](#) function if you want to specify custom delimiter. Also see notes for [CPLAtof\(\)](#) function.

Parameters

<i>nptr</i>	Pointer to string to convert.
<i>endptr</i>	If is not NULL, a pointer to the character after the last character used in the conversion is stored in the location referenced by <i>endptr</i> .

Returns

Converted value, if any.

10.1.2.54 `double CPL_DLL CPLStrtodDelim (const char * nptr, char ** endptr, char point)`

Converts ASCII string to floating point number using specified delimiter.

This function converts the initial portion of the string pointed to by *nptr* to double floating point representation. This function does the same as standard `strtod(3)`, but does not take locale in account. Instead of locale defined decimal delimiter you can specify your own one. Also see notes for [CPLAtof\(\)](#) function.

Parameters

<i>nptr</i>	Pointer to string to convert.
<i>endptr</i>	If is not NULL, a pointer to the character after the last character used in the conversion is stored in the location referenced by <i>endptr</i> .
<i>point</i>	Decimal delimiter.

Returns

Converted value, if any.

10.1.2.55 float CPL_DLL CPLStrtof (const char * *nptr*, char ** *endptr*)

Converts ASCII string to floating point number.

This function converts the initial portion of the string pointed to by *nptr* to single floating point representation. This function does the same as standard `strtof(3)`, but does not take locale in account. That means, the decimal delimiter is always '.' (decimal point). Use [CPLStrtofDelim\(\)](#) function if you want to specify custom delimiter. Also see notes for [CPLAtof\(\)](#) function.

Parameters

<i>nptr</i>	Pointer to string to convert.
<i>endptr</i>	If is not NULL, a pointer to the character after the last character used in the conversion is stored in the location referenced by <i>endptr</i> .

Returns

Converted value, if any.

10.1.2.56 float CPL_DLL CPLStrtofDelim (const char * *nptr*, char ** *endptr*, char *point*)

Converts ASCII string to floating point number using specified delimiter.

This function converts the initial portion of the string pointed to by *nptr* to single floating point representation. This function does the same as standard `strtof(3)`, but does not take locale in account. Instead of locale defined decimal delimiter you can specify your own one. Also see notes for [CPLAtof\(\)](#) function.

Parameters

<i>nptr</i>	Pointer to string to convert.
<i>endptr</i>	If is not NULL, a pointer to the character after the last character used in the conversion is stored in the location referenced by <i>endptr</i> .
<i>point</i>	Decimal delimiter.

Returns

Converted value, if any.

10.1.2.57 int CPL_DLL CPLUnlinkTree (const char * *pszPath*)

Returns

0 on successful completion, -1 if function fails.

10.2 cpl_error.h File Reference

```
#include "cpl_port.h"
```

Functions

- void CPL_DLL [CPLEmergencyError](#) (const char *)
- void CPL_DLL CPL_STDCALL [CPLErrorReset](#) (void)
- int CPL_DLL CPL_STDCALL [CPLGetLastErrorNo](#) (void)
- CPLErr CPL_DLL CPL_STDCALL [CPLGetLastErrorType](#) (void)
- const char CPL_DLL *CPL_STDCALL [CPLGetLastErrorMsg](#) (void)
- void *CPL_STDCALL [CPLGetErrorHandlerUserData](#) (void)
- CPLErrorHandler CPL_DLL CPL_STDCALL [CPLSetErrorHandler](#) (CPLErrorHandler)
- CPLErrorHandler CPL_DLL CPL_STDCALL [CPLSetErrorHandlerEx](#) (CPLErrorHandler, void *)
- void CPL_DLL CPL_STDCALL [CPLPushErrorHandler](#) (CPLErrorHandler)
- void CPL_DLL CPL_STDCALL [CPLPushErrorHandlerEx](#) (CPLErrorHandler, void *)
- void CPL_DLL CPL_STDCALL [CPLPopErrorHandler](#) (void)
- void CPL_DLL CPL_STDCALL void [CPLAssert](#) (const char *, const char *, int)

10.2.1 Detailed Description

CPL error handling services.

10.2.2 Function Documentation

10.2.2.1 void CPL_DLL CPL_STDCALL void CPL_DLL CPL_STDCALL [_CPLAssert](#) (const char * *pszExpression*, const char * *pszFile*, int *iLine*)

Report failure of a logical assertion.

Applications would normally use the [CPLAssert\(\)](#) macro which expands into code calling [_CPLAssert\(\)](#) only if the condition fails. [_CPLAssert\(\)](#) will generate a CE_Fatal error call to [CPLError\(\)](#), indicating the file name, and line number of the failed assertion, as well as containing the assertion itself.

There is no reason for application code to call [_CPLAssert\(\)](#) directly.

10.2.2.2 void CPL_DLL CPLEmergencyError (const char * *pszMessage*)

Fatal error when things are bad.

This function should be called in an emergency situation where it is unlikely that a regular error report would work. This would include in the case of heap exhaustion for even small allocations, or any failure in the process of reporting an error (such as TLS allocations).

This function should never return. After the error message has been reported as best possible, the application will abort() similarly to how [CPLError\(\)](#) aborts on CE_Fatal class errors.

Parameters

<i>pszMessage</i>	the error message to report.
-------------------	------------------------------

10.2.2.3 void CPL_DLL CPL_STDCALL CPLErrorReset(void)

Erase any traces of previous errors.

This is normally used to ensure that an error which has been recovered from does not appear to be still in play with high level functions.

10.2.2.4 void* CPL_STDCALL CPLGetErrorHandlerUserData(void)

Fetch the user data for the error context

Fetches the user data for the current error context. You can set the user data for the error context when you add your handler by issuing [CPLSetErrorHandlerEx\(\)](#) and [CPLPushErrorHandlerEx\(\)](#). Note that user data is primarily intended for providing context within error handlers themselves, but they could potentially be abused in other useful ways with the usual caveat emptor understanding.

Returns

the user data pointer for the error context

10.2.2.5 const char CPL_DLL* CPL_STDCALL CPLGetLastErrorMsg(void)

Get the last error message.

Fetches the last error message posted with [CPLError\(\)](#), that hasn't been cleared by [CPLErrorReset\(\)](#). The returned pointer is to an internal string that should not be altered or freed.

Returns

the last error message, or NULL if there is no posted error message.

10.2.2.6 int CPL_DLL CPL_STDCALL CPLGetLastErrorNo(void)

Fetch the last error number.

Fetches the last error number posted with [CPLError\(\)](#), that hasn't been cleared by [CPLErrorReset\(\)](#). This is the error number, not the error class.

Returns

the error number of the last error to occur, or CPLE_None (0) if there are no posted errors.

10.2.2.7 CPLerr CPL_DLL CPL_STDCALL CPLGetLastErrorType(void)

Fetch the last error type.

Fetches the last error type posted with [CPLError\(\)](#), that hasn't been cleared by [CPLErrorReset\(\)](#). This is the error class, not the error number.

Returns

the error type of the last error to occur, or CE_None (0) if there are no posted errors.

10.2.2.8 void CPL_DLL CPL_STDCALL CPLPopErrorHandler(void)

Pop error handler off stack.

Discards the current error handler on the error handler stack, and restores the one in use before the last [CPLPushErrorHandler\(\)](#) call. This method has no effect if there are no error handlers on the current threads error handler stack.

10.2.2.9 void CPL_DLL CPL_STDCALL CPLPushErrorHandler(CPLErrorHandler pfnErrorHandlerNew)

Push a new CPLError handler.

This pushes a new error handler on the thread-local error handler stack. This handler will be used until removed with [CPLPopErrorHandler\(\)](#).

The [CPLSetErrorHandler\(\)](#) docs have further information on how CPLError handlers work.

Parameters

<i>pfnErrorHandler-New</i>	new error handler function.
----------------------------	-----------------------------

10.2.2.10 void CPL_DLL CPL_STDCALL CPLPushErrorHandlerEx(CPLErrorHandler pfnErrorHandlerNew, void * pUserData)

Push a new CPLError handler with user data on the error context.

This pushes a new error handler on the thread-local error handler stack. This handler will be used until removed with [CPLPopErrorHandler\(\)](#). Obtain the user data back by using [CPLGetErrorHandler\(\)](#).

The [CPLSetErrorHandler\(\)](#) docs have further information on how CPLError handlers work.

Parameters

<i>pfnErrorHandler-New</i>	new error handler function.
<i>pUserData</i>	User data to put on the error context.

10.2.2.11 CPLErrorHandler CPL_DLL CPL_STDCALL CPLSetErrorHandler(CPLErrorHandler pfnErrorHandlerNew)

Install custom error handler.

Allow the library's user to specify his own error handler function. A valid error handler is a C function with the following prototype:

```
void MyErrorHandler(CPLErr eErrClass, int err_no, const char *msg)
```

Pass NULL to come back to the default behavior. The default behaviour ([CPLDefaultErrorHandler\(\)](#)) is to write the message to stderr.

The msg will be a partially formatted error message not containing the "ERROR %d:" portion emitted by the default handler. Message formatting is handled by [CPLError\(\)](#) before calling the handler. If the error handler function is passed a CE_Fatal class error and returns, then [CPLError\(\)](#) will call [abort\(\)](#). Applications wanting to interrupt this fatal behaviour will have to use [longjmp\(\)](#), or a C++ exception to indirectly exit the function.

Another standard error handler is [CPLQuietErrorHandler\(\)](#) which doesn't make any attempt to report the passed error or warning messages but will process debug messages via [CPLDefaultErrorHandler\(\)](#).

Note that error handlers set with [CPLSetErrorHandler\(\)](#) apply to all threads in an application, while error handlers set with [CPLPushErrorHandler](#) are thread-local. However, any error handlers pushed with [CPLPushErrorHandler](#)

(and not removed with CPLPopErrorHandler) take precedence over the global error handlers set with [CPLSetErrorHandler\(\)](#). Generally speaking [CPLSetErrorHandler\(\)](#) would be used to set a desired global error handler, while [CPLPushErrorHandler\(\)](#) would be used to install a temporary local error handler, such as CPLQuietErrorHandler() to suppress error reporting in a limited segment of code.

Parameters

<i>pfnErrorHandler-</i>	new error handler function.
<i>New</i>	

Returns

returns the previously installed error handler.

10.2.2.12 CPLErrorHandler CPL_DLL CPL_STDCALL CPLSetErrorHandlerEx (CPLErrorHandler *pfnErrorHandlerNew*, void * *pUserData*)

Install custom error handle with user's data. This method is essentially CPLSetErrorHandler with an added pointer to pUserData. The pUserData is not returned in the CPLErrorHandler, however, and must be fetched via CPLGetLastErrorUserData

Parameters

<i>pfnErrorHandler-</i>	new error handler function.
<i>New</i>	
<i>pUserData</i>	User data to carry along with the error context.

Returns

returns the previously installed error handler.

10.3 cpl_hash_set.h File Reference

```
#include "cpl_port.h"
```

Functions

- CPLHashSet CPL_DLL * [CPLHashSetNew](#) (CPLHashSetHashFunc fnHashFunc, CPLHashSetEqualFunc fnEqualFunc, CPLHashSetFreeElFunc fnFreeElFunc)
- void CPL_DLL [CPLHashSetDestroy](#) (CPLHashSet *set)
- int CPL_DLL [CPLHashSetSize](#) (const CPLHashSet *set)
- void CPL_DLL [CPLHashSetForeach](#) (CPLHashSet *set, CPLHashSetIterElFunc fnIterFunc, void *user_data)
- int CPL_DLL [CPLHashSetInsert](#) (CPLHashSet *set, void *elt)
- void CPL_DLL * [CPLHashSetLookup](#) (CPLHashSet *set, const void *elt)
- int CPL_DLL [CPLHashSetRemove](#) (CPLHashSet *set, const void *elt)
- unsigned long CPL_DLL [CPLHashSetHashPointer](#) (const void *elt)
- int CPL_DLL [CPLHashSetEqualPointer](#) (const void *elt1, const void *elt2)
- unsigned long CPL_DLL [CPLHashSetHashStr](#) (const void *pszStr)
- int CPL_DLL [CPLHashSetEqualStr](#) (const void *pszStr1, const void *pszStr2)

10.3.1 Detailed Description

Hash set implementation.

An hash set is a data structure that holds elements that are unique according to a comparison function. Operations on the hash set, such as insertion, removal or lookup, are supposed to be fast if an efficient "hash" function is provided.

10.3.2 Function Documentation

10.3.2.1 void CPL_DLL CPLHashSetDestroy (CPLHashSet * set)

Destroys an allocated hash set.

This function also frees the elements if a free function was provided at the creation of the hash set.

Parameters

<i>set</i>	the hash set
------------	--------------

10.3.2.2 int CPL_DLL CPLHashSetEqualPointer (const void * elt1, const void * elt2)

Equality function for arbitrary pointers

Parameters

<i>elt1</i>	the first arbitrary pointer to compare
<i>elt2</i>	the second arbitrary pointer to compare

Returns

TRUE if the pointers are equal

10.3.2.3 int CPL_DLL CPLHashSetEqualStr (const void * elt1, const void * elt2)

Equality function for strings

Parameters

<i>elt1</i>	the first string to compare. May be NULL.
<i>elt2</i>	the second string to compare. May be NULL.

Returns

TRUE if the strings are equal

10.3.2.4 void CPL_DLL CPLHashSetForeach (CPLHashSet * set, CPLHashSetIterFunc filterFunc, void * user_data)

Walk through the hash set and runs the provided function on all the elements

This function is provided the user_data argument of CPLHashSetForeach. It must return TRUE to go on the walk through the hash set, or FALSE to make it stop.

Note : the structure of the hash set must *NOT* be modified during the walk.

Parameters

<i>set</i>	the hash set.
<i>fnIterFunc</i>	the function called on each element.
<i>userData</i>	the user data provided to the function.

10.3.2.5 unsigned long CPL_DLL CPLHashSetHashPointer (const void * *elt*)

Hash function for an arbitrary pointer

Parameters

<i>elt</i>	the arbitrary pointer to hash
------------	-------------------------------

Returns

the hash value of the pointer

10.3.2.6 unsigned long CPL_DLL CPLHashSetHashStr (const void * *elt*)

Hash function for a zero-terminated string

Parameters

<i>elt</i>	the string to hash. May be NULL.
------------	----------------------------------

Returns

the hash value of the string

10.3.2.7 int CPL_DLL CPLHashSetInsert (CPLHashSet * *set*, void * *elt*)

Inserts an element into a hash set.

If the element was already inserted in the hash set, the previous element is replaced by the new element. If a free function was provided, it is used to free the previously inserted element

Parameters

<i>set</i>	the hash set
<i>elt</i>	the new element to insert in the hash set

Returns

TRUE if the element was not already in the hash set

10.3.2.8 void CPL_DLL* CPLHashSetLookup (CPLHashSet * *set*, const void * *elt*)

Returns the element found in the hash set corresponding to the element to look up. The element must not be modified.

Parameters

<i>set</i>	the hash set
<i>elt</i>	the element to look up in the hash set

Returns

the element found in the hash set or NULL

10.3.2.9 CPLHashSet CPL_DLL* CPLHashSetNew (CPLHashSetHashFunc *fnHashFunc*, CPLHashSetEqualFunc *fnEqualFunc*, CPLHashSetFreeEltFunc *fnFreeEltFunc*)

Creates a new hash set

The hash function must return a hash value for the elements to insert. If *fnHashFunc* is NULL, CPLHashSetHashPointer will be used.

The equal function must return if two elements are equal. If *fnEqualFunc* is NULL, CPLHashSetEqualPointer will be used.

The free function is used to free elements inserted in the hash set, when the hash set is destroyed, when elements are removed or replaced. If *fnFreeEltFunc* is NULL, elements inserted into the hash set will not be freed.

Parameters

<i>fnHashFunc</i>	hash function. May be NULL.
<i>fnEqualFunc</i>	equal function. May be NULL.
<i>fnFreeEltFunc</i>	element free function. May be NULL.

Returns

a new hash set

10.3.2.10 int CPL_DLL CPLHashSetRemove (CPLHashSet * *set*, const void * *elt*)

Removes an element from a hash set

Parameters

<i>set</i>	the hash set
<i>elt</i>	the new element to remove from the hash set

Returns

TRUE if the element was in the hash set

10.3.2.11 int CPL_DLL CPLHashSetSize (const CPLHashSet * *set*)

Returns the number of elements inserted in the hash set

Note: this is not the internal size of the hash set

Parameters

<i>set</i>	the hash set
------------	--------------

Returns

the number of elements in the hash set

10.4 cpl_http.h File Reference

```
#include "cpl_conv.h"
#include "cpl_string.h"
#include "cpl_vsip.h"
```

Classes

- struct [CPLMimePart](#)
- struct [CPLHTTPResult](#)

Functions

- int CPL_DLL [CPLHTTPEnabled](#) (void)
Return if CPLHTTP services can be usefull.
- [CPLHTTPResult](#) CPL_DLL * [CPLHTTPFetch](#) (const char *pszURL, char **papszOptions)
Fetch a document from an url and return in a string.
- void CPL_DLL [CPLHTTPCleanup](#) (void)
Cleanup function to call at application termination.
- void CPL_DLL [CPLHTTPDestroyResult](#) ([CPLHTTPResult](#) *psResult)
Clean the memory associated with the return value of [CPLHTTPFetch\(\)](#)
- int CPL_DLL [CPLHTTPParseMultipartMime](#) ([CPLHTTPResult](#) *psResult)
Parses a a MIME multipart message.

10.4.1 Detailed Description

Interface for downloading HTTP, FTP documents

10.4.2 Function Documentation

10.4.2.1 void CPL_DLL CPLHTTPDestroyResult ([CPLHTTPResult](#) * *psResult*)

Clean the memory associated with the return value of [CPLHTTPFetch\(\)](#)

Parameters

<i>psResult</i>	pointer to the return value of CPLHTTPFetch()
-----------------	---

10.4.2.2 int CPL_DLL CPLHTTPEnabled (void)

Return if CPLHTTP services can be usefull.

Those services depend on GDAL being build with libcurl support.

Returns

TRUE if libcurl support is enabled

10.4.2.3 CPLHTTPResult CPL_DLL* CPLHTTPFetch (const char * *pszURL*, char ** *papszOptions*)

Fetch a document from an url and return in a string.

Parameters

<i>pszURL</i>	valid URL recognized by underlying download library (libcurl)
<i>papszOptions</i>	<p>option list as a NULL-terminated array of strings. May be NULL. The following options are handled :</p> <ul style="list-style-type: none"> • TIMEOUT=val, where val is in seconds • HEADERS=val, where val is an extra header to use when getting a web page. For example "Accept: application/x-ogcwkt" • HTTPAUTH=[BASIC/NTLM/GSSNEGOTIATE/ANY] to specify an authentication scheme to use. • USERPWD=userid:password to specify a user and password for authentication • POSTFIELDS=val, where val is a nul-terminated string to be passed to the server with a POST request. • PROXY=val, to make requests go through a proxy server, where val is of the form proxy.-server.com:port_number • PROXYUSERPWD=val, where val is of the form username:password • CUSTOMREQUEST=val, where val is GET, PUT, POST, DELETE, etc.. (GDAL >= 1.9.-0)

Alternatively, if not defined in the *papszOptions* arguments, the PROXY and PROXYUSERPWD values are searched in the configuration options named GDAL_HTTP_PROXY and GDAL_HTTP_PROXYUSERPWD, as proxy configuration belongs to networking setup and makes more sense at the configuration option level than at the connection level.

Returns

a CPLHTTPResult* structure that must be freed by [CPLHTTPDestroyResult\(\)](#), or NULL if libcurl support is disabled

10.4.2.4 int CPL_DLL CPLHTTPParseMultipartMime (CPLHTTPResult * *psResult*)

Parses a a MIME multipart message.

This function will iterate over each part and put it in a separate element of the *pasMimePart* array of the provided *psResult* structure.

Parameters

<i>psResult</i>	pointer to the return value of CPLHTTPFetch()
-----------------	---

Returns

TRUE if the message contains MIME multipart message.

10.5 cpl_list.h File Reference

```
#include "cpl_port.h"
```

Classes

- struct [_CPLList](#)

Typedefs

- [typedef CPL_C_START struct _CPLList CPLList](#)

Functions

- [CPLList CPL_DLL * CPLListAppend \(CPLList *psList, void *pData\)](#)
- [CPLList CPL_DLL * CPLListInsert \(CPLList *psList, void *pData, int nPosition\)](#)
- [CPLList CPL_DLL * CPLListGetLast \(CPLList *psList\)](#)
- [CPLList CPL_DLL * CPLListGet \(CPLList *psList, int nPosition\)](#)
- [int CPL_DLL CPLListCount \(CPLList *psList\)](#)
- [CPLList CPL_DLL * CPLListRemove \(CPLList *psList, int nPosition\)](#)
- [void CPL_DLL CPLListDestroy \(CPLList *psList\)](#)
- [CPLList CPL_DLL * CPLListGetNext \(CPLList *psElement\)](#)
- [void CPL_DLL * CPLListGetData \(CPLList *psElement\)](#)

10.5.1 Detailed Description

Simplest list implementation. List contains only pointers to stored objects, not objects itself. All operations regarding allocation and freeing memory for objects should be performed by the caller.

10.5.2 Typedef Documentation

10.5.2.1 [typedef CPL_C_START struct _CPLList CPLList](#)

List element structure.

10.5.3 Function Documentation

10.5.3.1 [CPLList CPL_DLL* CPLListAppend \(CPLList * psList, void * pData \)](#)

Append an object list and return a pointer to the modified list. If the input list is NULL, then a new list is created.

Parameters

<i>psList</i>	pointer to list head.
<i>pData</i>	pointer to inserted data object. May be NULL.

Returns

pointer to the head of modified list.

10.5.3.2 [int CPL_DLL CPLListCount \(CPLList * psList \)](#)

Return the number of elements in a list.

Parameters

<i>psList</i>	pointer to list head.
---------------	-----------------------

Returns

number of elements in a list.

10.5.3.3 void CPL_DLL CPLListDestroy (CPLList * *psList*)

Destroy a list. Caller responsible for freeing data objects contained in list elements.

Parameters

<i>psList</i>	pointer to list head.
---------------	-----------------------

10.5.3.4 CPLList CPL_DLL* CPLListGet (CPLList * *psList*, int *nPosition*)

Return the pointer to the specified element in a list.

Parameters

<i>psList</i>	pointer to list head.
<i>nPosition</i>	the index of the element in the list, 0 being the first element

Returns

pointer to the specified element in a list.

10.5.3.5 void CPL_DLL* CPLListGetData (CPLList * *psElement*)

Return pointer to the data object contained in given list element.

Parameters

<i>psElement</i>	pointer to list element.
------------------	--------------------------

Returns

pointer to the data object contained in given list element.

10.5.3.6 CPLList CPL_DLL* CPLListGetLast (CPLList * *psList*)

Return the pointer to last element in a list.

Parameters

<i>psList</i>	pointer to list head.
---------------	-----------------------

Returns

pointer to last element in a list.

10.5.3.7 CPLList CPL_DLL* CPLListGetNext (CPLList * psElement)

Return the pointer to next element in a list.

Parameters

<i>psElement</i>	pointer to list element.
------------------	--------------------------

Returns

pointer to the list element preceded by the given element.

10.5.3.8 CPLList CPL_DLL* CPLListInsert (CPLList * psList, void * pData, int nPosition)

Insert an object into list at specified position (zero based). If the input list is NULL, then a new list is created.

Parameters

<i>psList</i>	pointer to list head.
<i>pData</i>	pointer to inserted data object. May be NULL.
<i>nPosition</i>	position number to insert an object.

Returns

pointer to the head of modified list.

10.5.3.9 CPLList CPL_DLL* CPLListRemove (CPLList * psList, int nPosition)

Remove the element from the specified position (zero based) in a list. Data object contained in removed element must be freed by the caller first.

Parameters

<i>psList</i>	pointer to list head.
<i>nPosition</i>	position number to delet an element.

Returns

pointer to the head of modified list.

10.6 cpl_minixml.h File Reference

```
#include "cpl_port.h"
```

Classes

- struct [CPLXMLNode](#)

TypeDefs

- typedef struct [CPLXMLNode](#) [CPLXMLNode](#)

Enumerations

- enum `CPLXMLNodeType` {
 `CXT_Element` = 0, `CXT_Text` = 1, `CXT_Attribute` = 2, `CXT_Comment` = 3,
`CXT_Literal` = 4 }

Functions

- `CPLXMLNode CPL_DLL * CPLParseXMLString (const char *)`
Parse an XML string into tree form.
- `void CPL_DLL CPLDestroyXMLNode (CPLXMLNode *)`
Destroy a tree.
- `CPLXMLNode CPL_DLL * CPLGetXMLNode (CPLXMLNode *poRoot, const char *pszPath)`
Find node by path.
- `CPLXMLNode CPL_DLL * CPLSearchXMLNode (CPLXMLNode *poRoot, const char *pszTarget)`
Search for a node in document.
- `const char CPL_DLL * CPLGetXMLValue (CPLXMLNode *poRoot, const char *pszPath, const char *pszDefault)`
Fetch element/attribute value.
- `CPLXMLNode CPL_DLL * CPLCreateXMLNode (CPLXMLNode *poParent, CPLXMLNodeType eType, const char *pszText)`
Create an document tree item.
- `char CPL_DLL * CPLSerializeXMLTree (CPLXMLNode *psNode)`
Convert tree into string document.
- `void CPL_DLL CPLAddXMLChild (CPLXMLNode *psParent, CPLXMLNode *psChild)`
Add child node to parent.
- `int CPL_DLL CPLRemoveXMLChild (CPLXMLNode *psParent, CPLXMLNode *psChild)`
Remove child node from parent.
- `void CPL_DLL CPLAddXMLSibling (CPLXMLNode *psOlderSibling, CPLXMLNode *psNewSibling)`
Add new sibling.
- `CPLXMLNode CPL_DLL * CPLCreateXMLElementAndValue (CPLXMLNode *psParent, const char *pszName, const char *pszValue)`
Create an element and text value.
- `CPLXMLNode CPL_DLL * CPLCloneXMLTree (CPLXMLNode *psTree)`
Copy tree.
- `int CPL_DLL CPLSetXMLValue (CPLXMLNode *psRoot, const char *pszPath, const char *pszValue)`
Set element value by path.
- `void CPL_DLL CPLStripXMLNamespace (CPLXMLNode *psRoot, const char *pszNameSpace, int bRecurse)`
Strip indicated namespaces.
- `void CPL_DLL CPLCleanXMLElementName (char *)`
Make string into safe XML token.
- `CPLXMLNode CPL_DLL * CPLParseXMLFile (const char *pszFilename)`
Parse XML file into tree.
- `int CPL_DLL CPLSerializeXMLTreeToFile (CPLXMLNode *psTree, const char *pszFilename)`
Write document tree to a file.

10.6.1 Detailed Description

Definitions for CPL mini XML Parser/Serializer.

10.6.2 Typedef Documentation

10.6.2.1 `typedef struct CPLXMLNode CPLXMLNode`

Document node structure.

This C structure is used to hold a single text fragment representing a component of the document when parsed. It should be allocated with the appropriate CPL function, and freed with [CPLDestroyXMLNode\(\)](#). The structure contents should not normally be altered by application code, but may be freely examined by application code.

Using the `psChild` and `psNext` pointers, a heirarchical tree structure for a document can be represented as a tree of `CPLXMLNode` structures.

10.6.3 Enumeration Type Documentation

10.6.3.1 `enum CPLXMLNodeType`

Enumerator:

- `CXT_Element`** Node is an element
- `CXT_Text`** Node is a raw text value
- `CXT_Attribute`** Node is attribute
- `CXT_Comment`** Node is an XML comment.
- `CXT_Literal`** Node is a special literal

10.6.4 Function Documentation

10.6.4.1 `void CPL_DLL CPLAddXMLChild (CPLXMLNode * psParent, CPLXMLNode * psChild)`

Add child node to parent.

The passed child is added to the list of children of the indicated parent. Normally the child is added at the end of the parents child list, but attributes (`CXT_Attribute`) will be inserted after any other attributes but before any other element type. Ownership of the child node is effectively assumed by the parent node. If the child has siblings (it's `psNext` is not NULL) they will be trimmed, but if the child has children they are carried with it.

Parameters

<code>psParent</code>	the node to attach the child to. May not be NULL.
<code>psChild</code>	the child to add to the parent. May not be NULL. Should not be a child of any other parent.

10.6.4.2 `void CPL_DLL CPLAddXMLSibling (CPLXMLNode * psOlderSibling, CPLXMLNode * psNewSibling)`

Add new sibling.

The passed `psNewSibling` is added to the end of siblings of the `psOlderSibling` node. That is, it is added to the end of the `psNext` chain. There is no special handling if `psNewSibling` is an attribute. If this is required, use [CPLAddXMLChild\(\)](#).

Parameters

<code>psOlderSibling</code>	the node to attach the sibling after.
<code>psNewSibling</code>	the node to add at the end of <code>psOlderSibling</code> 's <code>psNext</code> chain.

10.6.4.3 void CPL_DLL CPLCleanXMLElementName (char * *pszTarget*)

Make string into safe XML token.

Modifies a string in place to try and make it into a legal XML token that can be used as an element name. This is accomplished by changing any characters not legal in a token into an underscore.

NOTE: This function should implement the rules in section 2.3 of <http://www.w3.org/TR/xml11/> but it doesn't yet do that properly. We only do a rough approximation of that.

Parameters

<i>pszTarget</i>	the string to be adjusted. It is altered in place.
------------------	--

10.6.4.4 CPLXMLNode CPL_DLL* CPLCloneXMLTree (CPLXMLNode * *psTree*)

Copy tree.

Creates a deep copy of a [CPLXMLNode](#) tree.

Parameters

<i>psTree</i>	the tree to duplicate.
---------------	------------------------

Returns

a copy of the whole tree.

10.6.4.5 CPLXMLNode CPL_DLL* CPLCreateXMLElementAndValue (CPLXMLNode * *psParent*, const char * *pszName*, const char * *pszValue*)

Create an element and text value.

This is function is a convenient short form for:

```
CPLXMLNode *psTextNode;
CPLXMLNode *psElementNode;

psElementNode = CPLCreateXMLNode( psParent, CXT_Element, pszName );
psTextNode = CPLCreateXMLNode( psElementNode, CXT_Text, pszValue );

return psElementNode;
```

It creates a CXT_Element node, with a CXT_Text child, and attaches the element to the passed parent.

Parameters

<i>psParent</i>	the parent node to which the resulting node should be attached. May be NULL to keep as freestanding.
<i>pszName</i>	the element name to create.
<i>pszValue</i>	the text to attach to the element. Must not be NULL.

Returns

the pointer to the new element node.

10.6.4.6 CPLXMLNode CPL_DLL* CPLCreateXMLNode (CPLXMLNode * *poParent*, CPLXMLNodeType *eType*, const char * *pszText*)

Create an document tree item.

Create a single [CPLXMLNode](#) object with the desired value and type, and attach it as a child of the indicated parent.

Parameters

<i>poParent</i>	the parent to which this node should be attached as a child. May be NULL to keep as free standing.
<i>eType</i>	the type of the newly created node
<i>pszText</i>	the value of the newly created node

Returns

the newly created node, now owned by the caller (or parent node).

10.6.4.7 void CPL_DLL CPLDestroyXMLNode (CPLXMLNode * *psNode*)

Destroy a tree.

This function frees resources associated with a [CPLXMLNode](#) and all its children nodes.

Parameters

<i>psNode</i>	the tree to free.
---------------	-------------------

10.6.4.8 CPLXMLNode CPL_DLL* CPLGetXMLNode (CPLXMLNode * *psRoot*, const char * *pszPath*)

Find node by path.

Searches the document or subdocument indicated by *psRoot* for an element (or attribute) with the given path. The path should consist of a set of element names separated by dots, not including the name of the root element (*psRoot*). If the requested element is not found NULL is returned.

Attribute names may only appear as the last item in the path.

The search is done from the root nodes children, but all intermediate nodes in the path must be specified. Searching for "name" would only find a name element or attribute if it is a direct child of the root, not at any level in the subdocument.

If the *pszPath* is prefixed by "=" then the search will begin with the root node, and its siblings, instead of the root nodes children. This is particularly useful when searching within a whole document which is often prefixed by one or more "junk" nodes like the <?xml> declaration.

Parameters

<i>psRoot</i>	the subtree in which to search. This should be a node of type CXT_Element. NULL is safe.
<i>pszPath</i>	the list of element names in the path (dot separated).

Returns

the requested element node, or NULL if not found.

10.6.4.9 const char CPL_DLL* CPLGetXMLValue (CPLXMLNode * psRoot, const char * pszPath, const char * pszDefault)

Fetch element/attribute value.

Searches the document for the element/attribute value associated with the path. The corresponding node is internally found with [CPLGetXMLNode\(\)](#) (see there for details on path handling). Once found, the value is considered to be the first CXT_Text child of the node.

If the attribute/element search fails, or if the found node has no value then the passed default value is returned.

The returned value points to memory within the document tree, and should not be altered or freed.

Parameters

<i>psRoot</i>	the subtree in which to search. This should be a node of type CXT_Element. NULL is safe.
<i>pszPath</i>	the list of element names in the path (dot separated). An empty path means get the value of the psRoot node.
<i>pszDefault</i>	the value to return if a corresponding value is not found, may be NULL.

Returns

the requested value or pszDefault if not found.

10.6.4.10 CPLXMLNode CPL_DLL* CPLParseXMLFile (const char * pszFilename)

Parse XML file into tree.

The named file is opened, loaded into memory as a big string, and parsed with [CPLParseXMLString\(\)](#). Errors in reading the file or parsing the XML will be reported by CPLError().

The "large file" API is used, so XML files can come from virtualized files.

Parameters

<i>pszFilename</i>	the file to open.
--------------------	-------------------

Returns

NULL on failure, or the document tree on success.

10.6.4.11 CPLXMLNode CPL_DLL* CPLParseXMLString (const char * pszString)

Parse an XML string into tree form.

The passed document is parsed into a [CPLXMLNode](#) tree representation. If the document is not well formed XML then NULL is returned, and errors are reported via CPLError(). No validation beyond wellformedness is done. The [CPLParseXMLFile\(\)](#) convenience function can be used to parse from a file.

The returned document tree is owned by the caller and should be freed with [CPLDestroyXMLNode\(\)](#) when no longer needed.

If the document has more than one "root level" element then those after the first will be attached to the first as siblings (via the psNext pointers) even though there is no common parent. A document with no XML structure (no angle brackets for instance) would be considered well formed, and returned as a single CXT_Text node.

Parameters

<i>pszString</i>	the document to parse.
------------------	------------------------

Returns

parsed tree or NULL on error.

10.6.4.12 int CPL_DLL CPLRemoveXMLChild (CPLXMLNode * psParent, CPLXMLNode * psChild)

Remove child node from parent.

The passed child is removed from the child list of the passed parent, but the child is not destroyed. The child retains ownership of its own children, but is cleanly removed from the child list of the parent.

Parameters

<i>psParent</i>	the node to the child is attached to.
<i>psChild</i>	the child to remove.

Returns

TRUE on success or FALSE if the child was not found.

10.6.4.13 CPLXMLNode CPL_DLL* CPLSearchXMLNode (CPLXMLNode * psRoot, const char * pszElement)

Search for a node in document.

Searches the children (and potentially siblings) of the document passed in for the named element or attribute. To search following siblings as well as children, prefix the *pszElement* name with an equal sign. This function does an in-order traversal of the document tree. So it will first match against the current node, then its first child, that child's first child, and so on.

Use [CPLGetXMLNode\(\)](#) to find a specific child, or along a specific node path.

Parameters

<i>psRoot</i>	the subtree to search. This should be a node of type CXT_Element. NULL is safe.
<i>pszElement</i>	the name of the element or attribute to search for.

Returns

The matching node or NULL on failure.

10.6.4.14 char CPL_DLL* CPLSerializeXMLTree (CPLXMLNode * psNode)

Convert tree into string document.

This function converts a [CPLXMLNode](#) tree representation of a document into a flat string representation. White space indentation is used visually preserve the tree structure of the document. The returned document becomes owned by the caller and should be freed with [CPLFree\(\)](#) when no longer needed.

Parameters

<i>psNode</i>

Returns

the document on success or NULL on failure.

10.6.4.15 int CPL_DLL CPLSerializeXMLTreeToFile (CPLXMLNode * *psTree*, const char * *pszFilename*)

Write document tree to a file.

The passed document tree is converted into one big string (with [CPLSerializeXMLTree\(\)](#)) and then written to the named file. Errors writing the file will be reported by [CPLError\(\)](#). The source document tree is not altered. If the output file already exists it will be overwritten.

Parameters

<i>psTree</i>	the document tree to write.
<i>pszFilename</i>	the name of the file to write to.

Returns

TRUE on success, FALSE otherwise.

10.6.4.16 int CPL_DLL CPLSetXMLValue (CPLXMLNode * *psRoot*, const char * *pszPath*, const char * *pszValue*)

Set element value by path.

Find (or create) the target element or attribute specified in the path, and assign it the indicated value.

Any path elements that do not already exist will be created. The target nodes value (the first CXT_Text child) will be replaced with the provided value.

If the target node is an attribute instead of an element, the name should be prefixed with a #.

Example: `CPLSetXMLValue("Citation.Id.Description", "DOQ dataset"); CPLSetXMLValue("Citation.Id.-Description.#name", "doq");`

Parameters

<i>psRoot</i>	the subdocument to be updated.
<i>pszPath</i>	the dot seperated path to the target element/attribute.
<i>pszValue</i>	the text value to assign.

Returns

TRUE on success.

10.6.4.17 void CPL_DLL CPLStripXMLNamespace (CPLXMLNode * *psRoot*, const char * *pszNamespace*, int *bRecurse*)

Strip indicated namespaces.

The subdocument (*psRoot*) is recursively examined, and any elements with the indicated namespace prefix will have the namespace prefix stripped from the element names. If the passed namespace is NULL, then all namespace prefixes will be stripped.

Nodes other than elements should remain unaffected. The changes are made "in place", and should not alter any node locations, only the *pszValue* field of affected nodes.

Parameters

<i>psRoot</i>	the document to operate on.
<i>pszNamespace</i>	the name space prefix (not including colon), or NULL.
<i>bRecurse</i>	TRUE to recurse over whole document, or FALSE to only operate on the passed node.

10.7 cpl_odbc.h File Reference

```
#include "cpl_port.h"
#include <sql.h>
#include <sqlext.h>
#include <odbcinst.h>
#include "cpl_string.h"
```

Classes

- class [CPLODBCDriverInstaller](#)
- class [CPLODBCSession](#)
- class [CPLODBCStatement](#)

10.7.1 Detailed Description

ODBC Abstraction Layer (C++).

10.8 cpl_port.h File Reference

```
#include "cpl_config.h"
#include <stdio.h>
#include <stdlib.h>
#include <math.h>
#include <stdarg.h>
#include <string.h>
#include <ctype.h>
#include <limits.h>
#include <time.h>
#include <errno.h>
#include <locale.h>
```

Macros

- [#define CPL_LSBINT16PTR\(x\) \(\(*\(GByte*\)\(x\)\) | \(\(*\(GByte*\)\(\(x\)+1\)\) << 8\)\)](#)
- [#define CPL_LSBINT32PTR\(x\)](#)

10.8.1 Detailed Description

Core portability definitions for CPL.

10.8.2 Macro Definition Documentation

10.8.2.1 [#define CPL_LSBINT16PTR\(x \) \(\(*\(GByte*\)\(x\)\) | \(\(*\(GByte*\)\(\(x\)+1\)\) << 8\)\)](#)

Return a Int16 from the 2 bytes ordered in LSB order at address x

10.8.2.2 #define CPL_LSBINT32PTR(x)

Value:

```
(((*(GByte*) (x)) | ((* (GByte*) ((x)+1)) << 8) | \
    ((* (GByte*) ((x)+2)) << 16) | ((* (GByte*) ((x)+3)) \
    << 24))
```

Return a Int32 from the 4 bytes ordered in LSB order at address x

10.9 cpl_quad_tree.h File Reference

```
#include "cpl_port.h"
```

Classes

- struct [CPLRectObj](#)

Functions

- [CPLQuadTree](#) [CPL_DLL](#) * [CPLQuadTreeCreate](#) (const [CPLRectObj](#) **pGlobalBounds*, [CPLQuadTreeGetBoundsFunc](#) *pfnGetBounds*)
- void [CPL_DLL](#) [CPLQuadTreeDestroy](#) ([CPLQuadTree](#) **hQuadtree*)
- void [CPL_DLL](#) [CPLQuadTreeSetBucketCapacity](#) ([CPLQuadTree](#) **hQuadtree*, int *nBucketCapacity*)
- int [CPL_DLL](#) [CPLQuadTreeGetAdvisedMaxDepth](#) (int *nExpectedFeatures*)
- void [CPL_DLL](#) [CPLQuadTreeSetMaxDepth](#) ([CPLQuadTree](#) **hQuadtree*, int *nMaxDepth*)
- void [CPL_DLL](#) [CPLQuadTreeInsert](#) ([CPLQuadTree](#) **hQuadtree*, void **hFeature*)
- void [CPL_DLL](#) ** [CPLQuadTreeSearch](#) (const [CPLQuadTree](#) **hQuadtree*, const [CPLRectObj](#) **pAoi*, int **pnFeatureCount*)
- void [CPL_DLL](#) [CPLQuadTreeForeach](#) (const [CPLQuadTree](#) **hQuadtree*, [CPLQuadTreeForeachFunc](#) *pfnForeach*, void **pUserData*)

10.9.1 Detailed Description

Quad tree implementation.

A quadtree is a tree data structure in which each internal node has up to four children. Quadtrees are most often used to partition a two dimensional space by recursively subdividing it into four quadrants or regions

10.9.2 Function Documentation

10.9.2.1 [CPLQuadTree](#) [CPL_DLL](#)* [CPLQuadTreeCreate](#) (const [CPLRectObj](#) * *pGlobalBounds*, [CPLQuadTreeGetBoundsFunc](#) *pfnGetBounds*)

Create a new quadtree

Parameters

<i>pGlobalBounds</i>	a pointer to the global extent of all the elements that will be inserted
<i>pfnGetBounds</i>	a user provided function to get the bounding box of the inserted elements

Returns

a newly allocated quadtree

10.9.2.2 void CPL_DLL CPLQuadTreeDestroy (CPLQuadTree * *hQuadTree*)

Destroy a quadtree

Parameters

<i>hQuadTree</i>	the quad tree to destroy
------------------	--------------------------

10.9.2.3 void CPL_DLL CPLQuadTreeForEach (const CPLQuadTree * *hQuadTree*, CPLQuadTreeForEachFunc *pfnForEach*, void * *pUserData*)

Walk through the quadtree and runs the provided function on all the elements

This function is provided with the user_data argument of pfnForEach. It must return TRUE to go on the walk through the hash set, or FALSE to make it stop.

Note : the structure of the quadtree must *NOT* be modified during the walk.

Parameters

<i>hQuadTree</i>	the quad tree
<i>pfnForEach</i>	the function called on each element.
<i>pUserData</i>	the user data provided to the function.

10.9.2.4 int CPL_DLL CPLQuadTreeGetAdvisedMaxDepth (int *nExpectedFeatures*)

Returns the optimal depth of a quadtree to hold nExpectedFeatures

Parameters

<i>nExpected-Features</i>	the expected maximum number of elements to be inserted
---------------------------	--

Returns

the optimal depth of a quadtree to hold nExpectedFeatures

10.9.2.5 void CPL_DLL CPLQuadTreeInsert (CPLQuadTree * *hQuadTree*, void * *hFeature*)

Insert a feature into a quadtree

Parameters

<i>hQuadTree</i>	the quad tree
<i>hFeature</i>	the feature to insert

10.9.2.6 void CPL_DLL CPLQuadTreeSearch (const CPLQuadTree * *hQuadTree*, const CPLRectObj * *pAoi*, int * *pnFeatureCount*)**

Returns all the elements inserted whose bounding box intersects the provided area of interest

Parameters

<i>hQuadTree</i>	the quad tree
<i>pAoi</i>	the pointer to the area of interest
<i>pnFeatureCount</i>	the user data provided to the function.

Returns

an array of features that must be freed with CPLFree

10.9.2.7 void CPL_DLL CPLQuadTreeSetBucketCapacity (CPLQuadTree * *hQuadTree*, int *nBucketCapacity*)

Set the maximum capacity of a node of a quadtree. The default value is 8. Note that the maximum capacity will only be honoured if the features inserted have a point geometry. Otherwise it may be exceeded.

Parameters

<i>hQuadTree</i>	the quad tree
<i>nBucketCapacity</i>	the maximum capacity of a node of a quadtree

10.9.2.8 void CPL_DLL CPLQuadTreeSetMaxDepth (CPLQuadTree * *hQuadTree*, int *nMaxDepth*)

Set the maximum depth of a quadtree. By default, quad trees have no maximum depth, but a maximum bucket capacity.

Parameters

<i>hQuadTree</i>	the quad tree
<i>nMaxDepth</i>	the maximum depth allowed

10.10 cpl_string.h File Reference

```
#include "cpl_vsi.h"
#include "cpl_error.h"
#include "cpl_conv.h"
```

Functions

- int CPL_DLL **CSLCount** (char **papszStrList)
- void CPL_DLL CPL_STDCALL **CSLDestroy** (char **papszStrList)
- char CPL_DLL ** **CSLDuplicate** (char **papszStrList) CPL_WARN_UNUSED_RESULT
- char CPL_DLL ** **CSLMerge** (char **papszOrig, char **papszOverride) CPL_WARN_UNUSED_RESULT
Merge two lists.
- char CPL_DLL ** **CSLTokenizeString2** (const char *pszString, const char *pszDelimiter, int nCSLTFlags) CPL_WARN_UNUSED_RESULT
- char CPL_DLL ** **CSLLoad** (const char *pszFname) CPL_WARN_UNUSED_RESULT
- char CPL_DLL ** **CSLLoad2** (const char *pszFname, int nMaxLines, int nMaxCols, char **papszOptions) CPL_WARN_UNUSED_RESULT
- int CPL_DLL **CSLFindString** (char **, const char *)
- int CPL_DLL **CSLPartialFindString** (char **papszHaystack, const char *pszNeedle)
- int CPL_DLL **CSLFindName** (char **papszStrList, const char *pszName)
- int CPL_DLL **CSLTestBoolean** (const char *pszValue)

- const char CPL_DLL * [CPLParseNameValue](#) (const char *pszNameValue, char **ppszKey)
- char CPL_DLL ** [CSLSetNameValue](#) (char **papszStrList, const char *pszName, const char *pszValue) CPL_WARN_UNUSED_RESULT
- void CPL_DLL [CSLSetNameValueSeparator](#) (char **papszStrList, const char *pszSeparator)
- char CPL_DLL * [CPLEscapeString](#) (const char *pszString, int nLength, int nScheme) CPL_WARN_UNUSED_RESULT
- char CPL_DLL * [CPLUnescapeString](#) (const char *pszString, int *pnLength, int nScheme) CPL_WARN_UNUSED_RESULT
- char CPL_DLL * [CPLBinaryToHex](#) (int nBytes, const GByte *pabyData) CPL_WARN_UNUSED_RESULT
- GByte CPL_DLL * [CPLHexToBinary](#) (const char *pszHex, int *pnBytes) CPL_WARN_UNUSED_RESULT
- CPLValueType CPL_DLL [CPLGetValueType](#) (const char *pszValue)
- size_t CPL_DLL [CPLStrlcpy](#) (char *pszDest, const char *pszSrc, size_t nDestSize)
- size_t CPL_DLL [CPLStrlcat](#) (char *pszDest, const char *pszSrc, size_t nDestSize)
- size_t CPL_DLL [CPLStrnlen](#) (const char *pszStr, size_t nMaxLen)
- int CPL_DLL [CPLEncodingCharSize](#) (const char *pszEncoding)
- char CPL_DLL * [CPLRecode](#) (const char *pszSource, const char *pszSrcEncoding, const char *pszDstEncoding) CPL_WARN_UNUSED_RESULT
- char CPL_DLL * [CPLRecodeFromWChar](#) (const wchar_t *pwszSource, const char *pszSrcEncoding, const char *pszDstEncoding) CPL_WARN_UNUSED_RESULT
- wchar_t CPL_DLL * [CPLRecodeToWChar](#) (const char *pszSource, const char *pszSrcEncoding, const char *pszDstEncoding) CPL_WARN_UNUSED_RESULT
- int CPL_DLL [CPLIsUTF8](#) (const char *pabyData, int nLen)
- char CPL_DLL * [CPLForceToASCII](#) (const char *pabyData, int nLen, char chReplacementChar) CPL_WARN_UNUSED_RESULT

10.10.1 Detailed Description

Various convenience functions for working with strings and string lists.

A StringList is just an array of strings with the last pointer being NULL. An empty StringList may be either a NULL pointer, or a pointer to a pointer memory location with a NULL value.

A common convention for StringLists is to use them to store name/value lists. In this case the contents are treated like a dictionary of name/value pairs. The actual data is formatted with each string having the format "<name>-<value>" (though "=" is also an acceptable separator). A number of the functions in the file operate on name/value style string lists (such as [CSLSetNameValue\(\)](#), and [CSLFetchNameValue\(\)](#)).

To some extent the CPLStringList C++ class can be used to abstract managing string lists a bit but still be able to return them from C functions.

10.10.2 Function Documentation

10.10.2.1 char CPL_DLL* CPLBinaryToHex (int nBytes, const GByte * pabyData)

Binary to hexadecimal translation.

Parameters

<i>nBytes</i>	number of bytes of binary data in pabyData.
<i>pabyData</i>	array of data bytes to translate.

Returns

hexadecimal translation, zero terminated. Free with [CPLFree\(\)](#).

10.10.2.2 int CPL_DLL CPLEncodingCharSize (const char * *pszEncoding*)

Return bytes per character for encoding.

This function returns the size in bytes of the smallest character in this encoding. For fixed width encodings (ASCII, UCS-2, UCS-4) this is straight forward. For encodings like UTF8 and UTF16 which represent some characters as a sequence of atomic character sizes the function still returns the atomic character size (1 for UTF8, 2 for UTF16).

This function will return the correct value for well known encodings with corresponding CPL_ENC_ values. It may not return the correct value for other encodings even if they are supported by the underlying iconv or windows transliteration services. Hopefully it will improve over time.

Parameters

<i>pszEncoding</i>	the name of the encoding.
--------------------	---------------------------

Returns

the size of a minimal character in bytes or -1 if the size is unknown.

10.10.2.3 char CPL_DLL* CPLEscapeString (const char * *pszInput*, int *nLength*, int *nScheme*)

Apply escaping to string to preserve special characters.

This function will "escape" a variety of special characters to make the string suitable to embed within a string constant or to write within a text stream but in a form that can be reconstituted to its original form. The escaping will even preserve zero bytes allowing preservation of raw binary data.

CPL_ESC_BackslashQuotable(0): This scheme turns a binary string into a form suitable to be placed within double quotes as a string constant. The backslash, quote, '\0' and newline characters are all escaped in the usual C style.

CPL_ESC_XML(1): This scheme converts the '<', '>', '"' and '&' characters into their XML/HTML equivalent (<, >, " and &) making a string safe to embed as CDATA within an XML element. The '\0' is not escaped and should not be included in the input.

CPL_ESC_URL(2): Everything except alphanumerics and the underscore are converted to a percent followed by a two digit hex encoding of the character (leading zero supplied if needed). This is the mechanism used for encoding values to be passed in URLs.

CPL_ESC_SQL(3): All single quotes are replaced with two single quotes. Suitable for use when constructing literal values for SQL commands where the literal will be enclosed in single quotes.

CPL_ESC_CSV(4): If the values contains commas, semicolons, tabs, double quotes, or newlines it places in double quotes, and double quotes in the value are doubled. Suitable for use when constructing field values for .csv files. Note that [CPLUnescapeString\(\)](#) currently does not support this format, only [CPLEscapeString\(\)](#). See cpl_csv.cpp for csv parsing support.

Parameters

<i>pszInput</i>	the string to escape.
<i>nLength</i>	The number of bytes of data to preserve. If this is -1 the strlen(pszString) function will be used to compute the length.
<i>nScheme</i>	the encoding scheme to use.

Returns

an escaped, zero terminated string that should be freed with CPLFree() when no longer needed.

10.10.2.4 char CPL_DLL* CPLForceToASCII (const char * *pabyData*, int *nLen*, char *chReplacementChar*)

Return a new string that is made only of ASCII characters. If non-ASCII characters are found in the input string, they will be replaced by the provided replacement character.

Parameters

<i>pabyData</i>	input string to test
<i>nLen</i>	length of the input string, or -1 if the function must compute the string length. In which case it must be null terminated.
<i>chReplacement-Char</i>	character which will be used when the input stream contains a non ASCII character. Must be valid ASCII !

Returns

a new string that must be freed with CPLFree().

Since

GDAL 1.7.0

10.10.2.5 CPLValueType CPL_DLL CPLGetValueType (const char * *pszValue*)

Detect the type of the value contained in a string, whether it is a real, an integer or a string. Leading and trailing spaces are skipped in the analysis.

Note: in the context of this function, integer must be understood in a broad sense. It does not mean that the value can fit into a 32 bit integer for example. It might be larger.

Parameters

<i>pszValue</i>	the string to analyze
-----------------	-----------------------

Returns

returns the type of the value contained in the string.

10.10.2.6 GByte CPL_DLL* CPLHexToBinary (const char * *pszHex*, int * *pnBytes*)

Hexadecimal to binary translation

Parameters

<i>pszHex</i>	the input hex encoded string.
<i>pnBytes</i>	the returned count of decoded bytes placed here.

Returns

returns binary buffer of data - free with CPLFree().

10.10.2.7 int CPL_DLL CPLIsUTF8 (const char * *pabyData*, int *nLen*)

Test if a string is encoded as UTF-8.

Parameters

<i>pabyData</i>	input string to test
<i>nLen</i>	length of the input string, or -1 if the function must compute the string length. In which case it must be null terminated.

Returns

TRUE if the string is encoded as UTF-8. FALSE otherwise

Since

GDAL 1.7.0

10.10.2.8 const char CPL_DLL* CPLParseNameValuePair (const char * *pszNameValue*, char ** *ppszKey*)

Parse NAME=VALUE string into name and value components.

Note that if *ppszKey* is non-NULL, the key (or name) portion will be allocated using VSIMalloc(), and returned in that pointer. It is the applications responsibility to free this string, but the application should not modify or free the returned value portion.

This function also support "NAME:VALUE" strings and will strip white space from around the delimiter when forming name and value strings.

Eventually CSLFetchNameValuePair() and friends may be modified to use [CPLParseNameValuePair\(\)](#).

Parameters

<i>pszNameValue</i>	string in "NAME=VALUE" format.
<i>ppszKey</i>	optional pointer though which to return the name portion.

Returns

the value portion (pointing into original string).

10.10.2.9 char CPL_DLL* CPLRecode (const char * *pszSource*, const char * *pszSrcEncoding*, const char * *pszDstEncoding*)

Convert a string from a source encoding to a destination encoding.

The only guaranteed supported encodings are CPL_ENC_UTF8, CPL_ENC_ASCII and CPL_ENC_ISO8859_1. Currently, the following conversions are supported :

- CPL_ENC_ASCII -> CPL_ENC_UTF8 or CPL_ENC_ISO8859_1 (no conversion in fact)
- CPL_ENC_ISO8859_1 -> CPL_ENC_UTF8
- CPL_ENC_UTF8 -> CPL_ENC_ISO8859_1

If an error occurs an error may, or may not be posted with CPLError().

Parameters

<i>pszSource</i>	a NULL terminated string.
<i>pszSrcEncoding</i>	the source encoding.
<i>pszDstEncoding</i>	the destination encoding.

Returns

a NULL terminated string which should be freed with CPLFree().

Since

GDAL 1.6.0

10.10.2.10 `char CPL_DLL* CPLRecodeFromWChar (const wchar_t * pwszSource, const char * pszSrcEncoding, const char * pszDstEncoding)`

Convert wchar_t string to UTF-8.

Convert a wchar_t string into a multibyte utf-8 string. The only guaranteed supported source encoding is CPL_ENC_UCS2, and the only guaranteed supported destination encodings are CPL_ENC_UTF8, CPL_ENC_ASCII and CPL_ENC_ISO8859_1. In some cases (ie. using iconv()) other encodings may also be supported.

Note that the wchar_t type varies in size on different systems. On win32 it is normally 2 bytes, and on unix 4 bytes.

If an error occurs an error may, or may not be posted with CPLError().

Parameters

<code>pwszSource</code>	the source wchar_t string, terminated with a 0 wchar_t.
<code>pszSrcEncoding</code>	the source encoding, typically CPL_ENC_UCS2.
<code>pszDstEncoding</code>	the destination encoding, typically CPL_ENC_UTF8.

Returns

a zero terminated multi-byte string which should be freed with CPLFree(), or NULL if an error occurs.

Since

GDAL 1.6.0

10.10.2.11 `wchar_t CPL_DLL* CPLRecodeToWChar (const char * pszSource, const char * pszSrcEncoding, const char * pszDstEncoding)`

Convert UTF-8 string to a wchar_t string.

Convert a 8bit, multi-byte per character input string into a wide character (wchar_t) string. The only guaranteed supported source encodings are CPL_ENC_UTF8, CPL_ENC_ASCII and CPL_ENC_ISO8869_1 (LATIN1). The only guaranteed supported destination encoding is CPL_ENC_UCS2. Other source and destination encodings may be supported depending on the underlying implementation.

Note that the wchar_t type varies in size on different systems. On win32 it is normally 2 bytes, and on unix 4 bytes.

If an error occurs an error may, or may not be posted with CPLError().

Parameters

<code>pszSource</code>	input multi-byte character string.
<code>pszSrcEncoding</code>	source encoding, typically CPL_ENC_UTF8.
<code>pszDstEncoding</code>	destination encoding, typically CPL_ENC_UCS2.

Returns

the zero terminated wchar_t string (to be freed with CPLFree()) or NULL on error.

Since

GDAL 1.6.0

10.10.2.12 size_t CPL_DLL CPLStrlcat (char * pszDest, const char * pszSrc, size_t nDestSize)

Appends a source string to a destination buffer.

This function ensures that the destination buffer is always NUL terminated (provided that its length is at least 1 and that there is at least one byte free in pszDest, that is to say strlen(pszDest_before) < nDestSize)

This function is designed to be a safer, more consistent, and less error prone replacement for strncat. Its contract is identical to libbsd's strlcat.

Truncation can be detected by testing if the return value of CPLStrlcat is greater or equal to nDestSize.

```
char szDest[5];
CPLStrlcpy(szDest, "ab", sizeof(szDest));
if (CPLStrlcat(szDest, "cde", sizeof(szDest)) >= sizeof(szDest))
    fprintf(stderr, "truncation occured !\n");
```

Parameters

<i>pszDest</i>	destination buffer. Must be NUL terminated before running CPLStrlcat
<i>pszSrc</i>	source string. Must be NUL terminated
<i>nDestSize</i>	size of destination buffer (including space for the NUL terminator character)

Returns

the theoretical length of the destination string after concatenation (=strlen(pszDest_before) + strlen(pszSrc)). If strlen(pszDest_before) >= nDestSize, then it returns nDestSize + strlen(pszSrc)

Since

GDAL 1.7.0

10.10.2.13 size_t CPL_DLL CPLStrlcpy (char * pszDest, const char * pszSrc, size_t nDestSize)

Copy source string to a destination buffer.

This function ensures that the destination buffer is always NUL terminated (provided that its length is at least 1).

This function is designed to be a safer, more consistent, and less error prone replacement for strncpy. Its contract is identical to libbsd's strlcpy.

Truncation can be detected by testing if the return value of CPLStrlcpy is greater or equal to nDestSize.

```
char szDest[5];
if (CPLStrlcpy(szDest, "abcde", sizeof(szDest)) >= sizeof(szDest))
    fprintf(stderr, "truncation occured !\n");
```

Parameters

<i>pszDest</i>	destination buffer
<i>pszSrc</i>	source string. Must be NUL terminated
<i>nDestSize</i>	size of destination buffer (including space for the NUL terminator character)

Returns

the length of the source string (=strlen(pszSrc))

Since

GDAL 1.7.0

10.10.2.14 size_t CPL_DLL CPLStrnlen (const char * *pszStr*, size_t *nMaxLen*)

Returns the length of a NUL terminated string by reading at most the specified number of bytes.

The [CPLStrnlen\(\)](#) function returns MIN(strlen(pszStr), nMaxLen). Only the first nMaxLen bytes of the string will be read. Usefull to test if a string contains at least nMaxLen characters without reading the full string up to the NUL terminating character.

Parameters

<i>pszStr</i>	a NUL terminated string
<i>nMaxLen</i>	maximum number of bytes to read in pszStr

Returns

strlen(pszStr) if the length is lesser than nMaxLen, otherwise nMaxLen if the NUL character has not been found in the first nMaxLen bytes.

Since

GDAL 1.7.0

10.10.2.15 char CPL_DLL* CPLUnescapeString (const char * *pszInput*, int * *pnLength*, int *nScheme*)

Unescape a string.

This function does the opposite of [CPLEscapeString\(\)](#). Given a string with special values escaped according to some scheme, it will return a new copy of the string returned to it's original form.

Parameters

<i>pszInput</i>	the input string. This is a zero terminated string.
<i>pnLength</i>	location to return the length of the unescaped string, which may in some cases include embedded '\0' characters.
<i>nScheme</i>	the escaped scheme to undo (see CPLEscapeString() for a list).

Returns

a copy of the unescaped string that should be freed by the application using CPLFree() when no longer needed.

10.10.2.16 int CPL_DLL CSLCount (char ** *papszStrList*)

Return number of items in a string list.

Returns the number of items in a string list, not counting the terminating NULL. Passing in NULL is safe, and will result in a count of zero.

Lists are counted by iterating through them so long lists will take more time than short lists. Care should be taken to avoid using [CSLCount\(\)](#) as an end condition for loops as it will result in O(n^2) behavior.

Parameters

<i>papszStrList</i>	the string list to count.
---------------------	---------------------------

Returns

the number of entries.

10.10.2.17 void CPL_DLL CPL_STDCALL CSLDestroy (char ** *papszStrList*)

Free string list.

Frees the passed string list (null terminated array of strings). It is safe to pass NULL.

Parameters

<i>papszStrList</i>	the list to free.
---------------------	-------------------

10.10.2.18 char CPL_DLL CSLDuplicate (char ** *papszStrList*)**

Clone a string list.

Efficiently allocates a copy of a string list. The returned list is owned by the caller and should be freed with [CSL-Destroy\(\)](#).

Parameters

<i>papszStrList</i>	the input string list.
---------------------	------------------------

Returns

newly allocated copy.

10.10.2.19 int CPL_DLL CSLFindName (char ** *papszStrList*, const char * *pszName*)

Find StringList entry with given key name.

Parameters

<i>papszStrList</i>	the string list to search.
<i>pszName</i>	the key value to look for (case insensitive).

Returns

-1 on failure or the list index of the first occurrence matching the given key.

10.10.2.20 int CPL_DLL CSLFindString (char ** *papszList*, const char * *pszTarget*)

Find a string within a string list.

Returns the index of the entry in the string list that contains the target string. The string in the string list must be a full match for the target, but the search is case insensitive.

Parameters

<i>papszList</i>	the string list to be searched.
<i>pszTarget</i>	the string to be searched for.

Returns

the index of the string within the list or -1 on failure.

10.10.2.21 char CPL_DLL CSLLoad (const char * *pszFname*)**

Load a text file into a string list.

The VSI*L API is used, so [VSIFOpenL\(\)](#) supported objects that aren't physical files can also be accessed. Files are returned as a string list, with one item in the string list per line. End of line markers are stripped (by [CPLReadLineL\(\)](#)).

If reading the file fails a CPLError() will be issued and NULL returned.

Parameters

<i>pszFname</i>	the name of the file to read.
-----------------	-------------------------------

Returns

a string list with the files lines, now owned by caller. To be freed with [CSLDestroy\(\)](#)

10.10.2.22 char CPL_DLL CSLLoad2 (const char * *pszFname*, int *nMaxLines*, int *nMaxCols*, char ** *papszOptions*)**

Load a text file into a string list.

The VSI*L API is used, so [VSIFOpenL\(\)](#) supported objects that aren't physical files can also be accessed. Files are returned as a string list, with one item in the string list per line. End of line markers are stripped (by [CPLReadLineL\(\)](#)).

If reading the file fails a CPLError() will be issued and NULL returned.

Parameters

<i>pszFname</i>	the name of the file to read.
<i>nMaxLines</i>	maximum number of lines to read before stopping, or -1 for no limit.
<i>nMaxCols</i>	maximum number of characters in a line before stopping, or -1 for no limit.
<i>papszOptions</i>	NULL-terminated array of options. Unused for now.

Returns

a string list with the files lines, now owned by caller. To be freed with [CSLDestroy\(\)](#)

Since

GDAL 1.7.0

10.10.2.23 char CPL_DLL CSLMerge (char ** *papszOrig*, char ** *papszOverride*)**

Merge two lists.

The two lists are merged, ensuring that if any keys appear in both that the value from the second (*papszOverride*) list take precedence.

Parameters

<i>papszOrig</i>	the original list, being modified.
<i>papszOverride</i>	the list of items being merged in. This list is unaltered and remains owned by the caller.

Returns

updated list.

10.10.2.24 int CPL_DLL CSLPartialFindString (char ** *papszHaystack*, const char * *pszNeedle*)

Find a substring within a string list.

Returns the index of the entry in the string list that contains the target string as a substring. The search is case sensitive (unlike [CSLFindString\(\)](#)).

Parameters

<i>papszHaystack</i>	the string list to be searched.
<i>pszNeedle</i>	the substring to be searched for.

Returns

the index of the string within the list or -1 on failure.

10.10.2.25 char CPL_DLL CSLSetNameValue (char ** *papszList*, const char * *pszName*, const char * *pszValue*)**

Assign value to name in StringList.

Set the value for a given name in a StringList of "Name=Value" pairs ("Name:Value" pairs are also supported for backward compatibility with older stuff.)

If there is already a value for that name in the list then the value is changed, otherwise a new "Name=Value" pair is added.

Parameters

<i>papszList</i>	the original list, the modified version is returned.
<i>pszName</i>	the name to be assigned a value. This should be a well formed token (no spaces or very special characters).
<i>pszValue</i>	the value to assign to the name. This should not contain any newlines (CR or LF) but is otherwise pretty much unconstrained. If NULL any corresponding value will be removed.

Returns

modified stringlist.

10.10.2.26 void CPL_DLL CSLSetNameValueSeparator (char ** *papszList*, const char * *pszSeparator*)

Replace the default separator (":" or "=") with the passed separator in the given name/value list.

Note that if a separator other than ":" or "=" is used, the resulting list will not be manipulatable by the CSL name/value functions any more.

The [CPLParseNameValuePair\(\)](#) function is used to break the existing lines, and it also strips white space from around the existing delimiter, thus the old separator, and any white space will be replaced by the new separator. For formatting purposes it may be desireable to include some white space in the new separator. eg. ":" or " = ".

Parameters

<i>papszList</i>	the list to update. Component strings may be freed but the list array will remain at the same location.
<i>pszSeparator</i>	the new separator string to insert.

10.10.2.27 int CPL_DLL CSLTestBoolean (const char * *pszValue*)

Test what boolean value contained in the string.

If *pszValue* is "NO", "FALSE", "OFF" or "0" will be returned FALSE. Otherwise, TRUE will be returned.

Parameters

<i>pszValue</i>	the string should be tested.
-----------------	------------------------------

Returns

TRUE or FALSE.

10.10.2.28 char CPL_DLL CSLTokenizeString2 (const char * *pszString*, const char * *pszDelimiters*, int *nCSLTFlags*)**

Tokenize a string.

This function will split a string into tokens based on specified' delimiter(s) with a variety of options. The returned result is a string list that should be freed with [CSLDestroy\(\)](#) when no longer needed.

The available parsing options are:

- CSLT_ALLOWEMPTYTOKENS: allow the return of empty tokens when two delimiters in a row occur with no other text between them. If not set, empty tokens will be discarded;
- CSLT_STRIPLEADSPACES: strip leading space characters from the token (as reported by isspace());
- CSLT_STRIPENDSPACES: strip ending space characters from the token (as reported by isspace());
- CSLT_HONOURSTRINGS: double quotes can be used to hold values that should not be broken into multiple tokens;
- CSLT_PRESERVEQUOTES: string quotes are carried into the tokens when this is set, otherwise they are removed;
- CSLT_PRESERVEESCAPES: if set backslash escapes (for backslash itself, and for literal double quotes) will be preserved in the tokens, otherwise the backslashes will be removed in processing.

Example:

Parse a string into tokens based on various white space (space, newline, tab) and then print out results and cleanup. Quotes may be used to hold white space in tokens.

```
char **papszTokens;
int i;

papszTokens =
    CSLTokenizeString2( pszCommand, " \t\n",
                        CSLT_HONOURSTRINGS | CSLT_ALLOWEMPTYTOKENS );

for( i = 0; papszTokens != NULL && papszTokens[i] != NULL; i++ )
    printf( "arg %d: '%s'", papszTokens[i] );
CSLDestroy( papszTokens );
```

Parameters

<i>pszString</i>	the string to be split into tokens.
<i>pszDelimiters</i>	one or more characters to be used as token delimiters.
<i>nCSLTFlags</i>	an ORing of one or more of the CSLT_flag values.

Returns

a string list of tokens owned by the caller.

10.11 cpl_vsi.h File Reference

```
#include "cpl_port.h"
#include <unistd.h>
#include <sys/stat.h>
```

Functions

- VSILFILE CPL_DLL * [VSIFOpenL](#) (const char *, const char *) CPL_WARN_UNUSED_RESULT
Open file.
- int CPL_DLL [VSIFCloseL](#) (VSILFILE *)
Close file.
- int CPL_DLL [VSIFSeekL](#) (VSILFILE *, vsi_l_offset, int)
Seek to requested offset.
- vsi_l_offset CPL_DLL [VSIFTellL](#) (VSILFILE *)
Tell current file offset.
- size_t CPL_DLL [VSIFReadL](#) (void *, size_t, size_t, VSILFILE *)
Read bytes from file.
- int CPL_DLL [VSIFReadMultiRangeL](#) (int nRanges, void **ppData, const vsi_l_offset *panOffsets, const size_t *panSizes, VSILFILE *)
Read several ranges of bytes from file.
- size_t CPL_DLL [VSIFWriteL](#) (const void *, size_t, size_t, VSILFILE *)
Write bytes to file.
- int CPL_DLL [VSIEofL](#) (VSILFILE *)
Test for end of file.
- int CPL_DLL [VSIFTruncateL](#) (VSILFILE *, vsi_l_offset)
Truncate/expand the file to the specified size.
- int CPL_DLL [VSIFFlushL](#) (VSILFILE *)
Flush pending writes to disk.
- int CPL_DLL [VSIStatL](#) (const char *, VSIStatBufL *)
Get filesystem object info.
- int CPL_DLL [VSIStatExL](#) (const char *pszFilename, VSIStatBufL *psStatBuf, int nFlags)
Get filesystem object info.
- int CPL_DLL [VSIsCaseSensitiveFS](#) (const char *pszFilename)
Returns if the filenames of the filesystem are case sensitive.
- void CPL_DLL * [VSIMalloc2](#) (size_t nSize1, size_t nSize2) CPL_WARN_UNUSED_RESULT
- void CPL_DLL * [VSIMalloc3](#) (size_t nSize1, size_t nSize2, size_t nSize3) CPL_WARN_UNUSED_RESULT
- char CPL_DLL ** [VSIReadDir](#) (const char *)
Read names in a directory.
- int CPL_DLL [VSIMkdir](#) (const char *pathname, long mode)
Create a directory.

- int CPL_DLL [VSIRmdir](#) (const char *pathname)
Delete a directory.
- int CPL_DLL [VSIUnlink](#) (const char *pathname)
Delete a file.
- int CPL_DLL [VSIRename](#) (const char *oldpath, const char *newpath)
Rename a file.
- void CPL_DLL [VSInstallMemFileHandler](#) (void)
Install "memory" file system handler.
- void CPL_DLL [VSInstallSubFileHandler](#) (void)
- void [VSInstallGZipFileHandler](#) (void)
Install GZip file system handler.
- void [VSInstallZipFileHandler](#) (void)
Install ZIP file system handler.
- void [VSInstallStdinHandler](#) (void)
Install /vsistdin/ file system handler.
- void [VSInstallStdoutHandler](#) (void)
Install /vsistdout/ file system handler.
- void CPL_DLL [VSInstallSparseFileHandler](#) (void)
- void [VSInstallTarFileHandler](#) (void)
Install /vsitar/ file system handler.
- VSILFILE CPL_DLL * [VSIFileFromMemBuffer](#) (const char *pszFilename, GByte *pabyData, vsi_l_offset n-DataLength, int bTakeOwnership)
Create memory "file" from a buffer.
- GByte CPL_DLL * [VSIGetMemFileBuffer](#) (const char *pszFilename, vsi_l_offset *pnDataLength, int bUnlink-AndSeize)
Fetch buffer underlying memory file.

10.11.1 Detailed Description

Standard C Covers

The VSI functions are intended to be hookable aliases for Standard C I/O, memory allocation and other system functions. They are intended to allow virtualization of disk I/O so that non file data sources can be made to appear as files, and so that additional error trapping and reporting can be interested. The memory access API is aliased so that special application memory management services can be used.

It is intended that each of these functions retains exactly the same calling pattern as the original Standard C functions they relate to. This means we don't have to provide custom documentation, and also means that the default implementation is very simple.

10.11.2 Function Documentation

10.11.2.1 int CPL_DLL VSIFCloseL (VSILFILE * fp)

Close file.

This function closes the indicated file.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX `fclose()` function.

Parameters

<i>fp</i>	file handle opened with VSIFOpenL() .
-----------	---

Returns

0 on success or -1 on failure.

10.11.2.2 int CPL_DLL VSIFEOF(VSILFILE * fp)

Test for end of file.

Returns TRUE (non-zero) if an end-of-file condition occurred during the previous read operation. The end-of-file flag is cleared by a successful [VSIFSeekL\(\)](#) call.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX feof() call.

Parameters

<i>fp</i>	file handle opened with VSIFOpenL() .
-----------	---

Returns

TRUE if at EOF else FALSE.

10.11.2.3 int CPL_DLL VSIFFLUSH(VSILFILE * fp)

Flush pending writes to disk.

For files in write or update mode and on filesystem types where it is applicable, all pending output on the file is flushed to the physical disk.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX fflush() call.

Parameters

<i>fp</i>	file handle opened with VSIFOpenL() .
-----------	---

Returns

0 on success or -1 on error.

10.11.2.4 VSILFILE CPL_DLL* VSIFileFromMemBuffer(const char * pszFilename, GByte * pabyData, vsi_l_offset nDataLength, int bTakeOwnership)

Create memory "file" from a buffer.

A virtual memory file is created from the passed buffer with the indicated filename. Under normal conditions the filename would need to be absolute and within the /vsimem/ portion of the filesystem.

If bTakeOwnership is TRUE, then the memory file system handler will take ownership of the buffer, freeing it when the file is deleted. Otherwise it remains the responsibility of the caller, but should not be freed as long as it might be accessed as a file. In no circumstances does this function take a copy of the pabyData contents.

Parameters

<i>pszFilename</i>	the filename to be created.
<i>pabyData</i>	the data buffer for the file.
<i>nDataLength</i>	the length of buffer in bytes.
<i>bTakeOwnership</i>	TRUE to transfer "ownership" of buffer or FALSE.

Returns

open file handle on created file (see [VSIFOpenL\(\)](#)).

10.11.2.5 VSILFILE CPL_DLL* VSIFOpenL (const char * *pszFilename*, const char * *pszAccess*)

Open file.

This function opens a file with the desired access. Large files (larger than 2GB) should be supported. Binary access is always implied and the "b" does not need to be included in the *pszAccess* string.

Note that the "VSILFILE *" returned since GDAL 1.8.0 by this function is *NOT* a standard C library FILE *, and cannot be used with any functions other than the "VSI*L" family of functions. They aren't "real" FILE objects.

On windows it is possible to define the configuration option GDAL_FILE_IS_UTF8 to have *pszFilename* treated as being in the local encoding instead of UTF-8, restoring the pre-1.8.0 behavior of [VSIFOpenL\(\)](#).

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX fopen() function.

Parameters

<i>pszFilename</i>	the file to open. UTF-8 encoded.
<i>pszAccess</i>	access requested (ie. "r", "r+", "w").

Returns

NULL on failure, or the file handle.

10.11.2.6 size_t CPL_DLL VSIFReadL (void * *pBuffer*, size_t *nSize*, size_t *nCount*, VSILFILE * *fp*)

Read bytes from file.

Reads *nCount* objects of *nSize* bytes from the indicated file at the current offset into the indicated buffer.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX fread() call.

Parameters

<i>pBuffer</i>	the buffer into which the data should be read (at least <i>nCount</i> * <i>nSize</i> bytes in size).
<i>nSize</i>	size of objects to read in bytes.
<i>nCount</i>	number of objects to read.
<i>fp</i>	file handle opened with VSIFOpenL() .

Returns

number of objects successfully read.

10.11.2.7 int CPL_DLL VSIFReadMultiRangeL (int *nRanges*, void ** *ppData*, const vsi_l_offset * *panOffsets*, const size_t * *panSizes*, VSILFILE * *fp*)

Read several ranges of bytes from file.

Reads *nRanges* objects of *panSizes[i]* bytes from the indicated file at the offset *panOffsets[i]* into the buffer *ppData[i]*.

Ranges must be sorted in ascending start offset, and must not overlap each other.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory or /vsicurl/.

Parameters

<i>nRanges</i>	number of ranges to read.
<i>ppData</i>	array of <i>nRanges</i> buffer into which the data should be read (<i>ppData[i]</i> must be at list <i>panSizes[i]</i> bytes).
<i>panOffsets</i>	array of <i>nRanges</i> offsets at which the data should be read.
<i>panSizes</i>	array of <i>nRanges</i> sizes of objects to read (in bytes).
<i>fp</i>	file handle opened with VSIFOpenL() .

Returns

0 in case of success, -1 otherwise.

Since

GDAL 1.9.0

10.11.2.8 int CPL_DLL VSIFSeekL (VSILFILE * *fp*, vsi_l_offset *nOffset*, int *nWhence*)

Seek to requested offset.

Seek to the desired offset (*nOffset*) in the indicated file.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX fseek() call.

Parameters

<i>fp</i>	file handle opened with VSIFOpenL() .
<i>nOffset</i>	offset in bytes.
<i>nWhence</i>	one of SEEK_SET, SEEK_CUR or SEEK_END.

Returns

0 on success or -1 one failure.

10.11.2.9 vsi_l_offset CPL_DLL VSIFTellL (VSILFILE * *fp*)

Tell current file offset.

Returns the current file read/write offset in bytes from the beginning of the file.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX ftell() call.

Parameters

<i>fp</i>	file handle opened with VSIFOpenL() .
-----------	---

Returns

file offset in bytes.

10.11.2.10 int CPL_DLL VSIFTruncateL (VSILFILE * *fp*, vsi_l_offset *nNewSize*)

Truncate/expand the file to the specified size.

This method goes through the VSIFFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX ftruncate() call.

Parameters

<i>fp</i>	file handle opened with VSIFOpenL() .
<i>nNewSize</i>	new size in bytes.

Returns

0 on success

Since

GDAL 1.9.0

10.11.2.11 size_t CPL_DLL VSIFWriteL (const void * *pBuffer*, size_t *nSize*, size_t *nCount*, VSILFILE * *fp*)

Write bytes to file.

Writess *nCount* objects of *nSize* bytes to the indicated file at the current offset into the indicated buffer.

This method goes through the VSIFFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX fwrite() call.

Parameters

<i>pBuffer</i>	the buffer from which the data should be written (at least <i>nCount</i> * <i>nSize</i> bytes in size).
<i>nSize</i>	size of objects to read in bytes.
<i>nCount</i>	number of objects to read.
<i>fp</i>	file handle opened with VSIFOpenL() .

Returns

number of objects successfully written.

10.11.2.12 GByte CPL_DLL* VSIGetMemFileBuffer (const char * *pszFilename*, vsi_l_offset * *pnDataLength*, int *bUnlinkAndSeize*)

Fetch buffer underlying memory file.

This function returns a pointer to the memory buffer underlying a virtual "in memory" file. If bUnlinkAndSeize is TRUE the filesystem object will be deleted, and ownership of the buffer will pass to the caller otherwise the underlying file will remain in existence.

Parameters

<i>pszFilename</i>	the name of the file to grab the buffer of.
<i>pnDataLength</i>	(file) length returned in this variable.
<i>bUnlinkAndSeize</i>	TRUE to remove the file, or FALSE to leave unaltered.

Returns

pointer to memory buffer or NULL on failure.

10.11.2.13 void VSInstallGZipFileHandler (void)

Install GZip file system handler.

A special file handler is installed that allows reading on-the-fly and writing in GZip (.gz) files.

All portions of the file system underneath the base path "/vsigzip/" will be handled by this driver.

Additional documentation is to be found at <http://trac.osgeo.org/gdal/wiki/UserDocs/ReadIn-Zip>

Since

GDAL 1.6.0

10.11.2.14 void CPL_DLL VSInstallMemFileHandler (void)

Install "memory" file system handler.

A special file handler is installed that allows block of memory to be treated as files. All portions of the file system underneath the base path "/vsimem/" will be handled by this driver.

Normal VSI*L functions can be used freely to create and destroy memory arrays treating them as if they were real file system objects. Some additional methods exist to efficiently create memory file system objects without duplicating original copies of the data or to "steal" the block of memory associated with a memory file.

At this time the memory handler does not properly handle directory semantics for the memory portion of the file system. The [VSIReadDir\(\)](#) function is not supported though this will be corrected in the future.

Calling this function repeatedly should do no harm, though it is not necessary. It is already called the first time a virtualizable file access function (ie. [VSIFOpenL\(\)](#), [VSIMkDir\(\)](#), etc) is called.

This code example demonstrates using GDAL to translate from one memory buffer to another.

```
GByte *ConvertBufferFormat( GByte *pabyInData, vsi_l_offset nInDataLength,
                           vsi_l_offset *pnOutDataLength )
{
    // create memory file system object from buffer.
    VSIFCloseL( VSIFFileFromMemBuffer( "
/vsimem/work.dat", pabyInData,
nInDataLength, FALSE ) );

    // Open memory buffer for read.
    GDALDatasetH hDS = GDALOpen( "/vsimem/work.dat", GA_ReadOnly );

    // Get output format driver.
    GDALDriverH hDriver = GDALGetDriverByName( "GTiff" );
    GDALDatasetH hOutDS;

    hOutDS = GDALCreateCopy( hDriver, "/vsimem/out.tif", hDS, TRUE, NULL,
NULL, NULL );
}
```

```

// close source file, and "unlink" it.
GDALClose( hDS );
VSIUnlink( "/vsimem/work.dat" );

// seize the buffer associated with the output file.

return VSIGetMemFileBuffer( "/vsimem/out.tif",
    pnOutDataLength, TRUE );
}

```

10.11.2.15 void CPL_DLL VSInstallSparseFileHandler (void)

Install /vsispars/ virtual file handler.

The sparse virtual file handler allows a virtual file to be composed from chunks of data in other files, potentially with large spaces in the virtual file set to a constant value. This can make it possible to test some sorts of operations on what seems to be a large file with image data set to a constant value. It is also helpful when wanting to add test files to the test suite that are too large, but for which most of the data can be ignored. It could, in theory, also be used to treat several files on different file systems as one large virtual file.

The file referenced by /vsispars/ should be an XML control file formatted something like:

```

<VSISparseFile>
    <Length>87629264</Length>
    <SubfileRegion> Stuff at start of file.
        <Filename relative="1">251_head.dat</Filename>
        <DestinationOffset>0</DestinationOffset>
        <SourceOffset>0</SourceOffset>
        <RegionLength>2768</RegionLength>
    </SubfileRegion>

    <SubfileRegion> RasterDMS node.
        <Filename relative="1">251_rasterdms.dat</Filename>
        <DestinationOffset>87313104</DestinationOffset>
        <SourceOffset>0</SourceOffset>
        <RegionLength>160</RegionLength>
    </SubfileRegion>

    <SubfileRegion> Stuff at end of file.
        <Filename relative="1">251_tail.dat</Filename>
        <DestinationOffset>87611924</DestinationOffset>
        <SourceOffset>0</SourceOffset>
        <RegionLength>17340</RegionLength>
    </SubfileRegion>

    <ConstantRegion> Default for the rest of the file.
        <DestinationOffset>0</DestinationOffset>
        <RegionLength>87629264</RegionLength>
        <Value>0</Value>
    </ConstantRegion>
</VSISparseFile>

```

Hopefully the values and semantics are fairly obvious.

This driver is installed by default.

10.11.2.16 void VSInstallStdinHandler (void)

Install /vsistdin/ file system handler.

A special file handler is installed that allows reading from the standard input stream.

The file operations available are of course limited to Read() and forward Seek() (full seek in the first MB of a file).

Since

GDAL 1.8.0

10.11.2.17 void VSInstallStdoutHandler(void)

Install /vsistdout/ file system handler.

A special file handler is installed that allows writing to the standard output stream.

The file operations available are of course limited to Write().

Since

GDAL 1.8.0

10.11.2.18 void CPL_DLL VSInstallSubFileHandler(void)

Install /vsisubfile/ virtual file handler.

This virtual file system handler allows access to subregions of files, treating them as a file on their own to the virtual file system functions ([VSIFOpenL\(\)](#), etc).

A special form of the filename is used to indicate a subportion of another file:

/vsisubfile/<offset>[_<size>],<filename>

The size parameter is optional. Without it the remainder of the file from the start offset as treated as part of the subfile. Otherwise only <size> bytes from <offset> are treated as part of the subfile. The <filename> portion may be a relative or absolute path using normal rules. The <offset> and <size> values are in bytes.

eg. /vsisubfile/1000_3000,/data/abc.ntf /vsisubfile/5000,../xyz/raw.dat

Unlike the /vsimem/ or conventional file system handlers, there is no meaningful support for filesystem operations for creating new files, traversing directories, and deleting files within the /vsisubfile/ area. Only the [VSISStatL\(\)](#), [VSIFOpenL\(\)](#) and operations based on the file handle returned by [VSIFOpenL\(\)](#) operate properly.

10.11.2.19 void VSInstallTarFileHandler(void)

Install /vsitar/ file system handler.

A special file handler is installed that allows reading on-the-fly in TAR (regular .tar, or compressed .tar.gz/.tgz) archives.

All portions of the file system underneath the base path "/vsitar/" will be handled by this driver.

The syntax to open a file inside a zip file is /vsitar/path/to/the/file.tar/path/inside/the/tar/file were path/to/the/file.tar is relative or absolute and path/inside/the/tar/file is the relative path to the file inside the archive.

If the path is absolute, it should begin with a / on a Unix-like OS (or C:\ on Windows), so the line looks like /vsitar//home/gdal/... For example gdalinfo /vsitar/myarchive.tar/subdir1/file1.tif

Syntactic sugar : if the tar archive contains only one file located at its root, just mentionning "/vsitar/path/to/the/file.tar" will work

[VSISStatL\(\)](#) will return the uncompressed size in st_size member and file nature- file or directory - in st_mode member.

Directory listing is available through [VSIReadDir\(\)](#).

Since

GDAL 1.8.0

10.11.2.20 void VSInstallZipFileHandler(void)

Install ZIP file system handler.

A special file handler is installed that allows reading on-the-fly in ZIP (.zip) archives.

All portions of the file system underneath the base path "/vsizip/" will be handled by this driver.

The syntax to open a file inside a zip file is /vsizip/path/to/the/file.zip/path/inside/the/zip/file were path/to/the/file.zip is relative or absolute and path/inside/the/zip/file is the relative path to the file inside the archive.

If the path is absolute, it should begin with a / on a Unix-like OS (or C:\ on Windows), so the line looks like /vsizip//home/gdal/... For example gdalinfo vsizip/myarchive.zip/subdir1/file1.tif

Syntactic sugar : if the .zip file contains only one file located at its root, just mentionning "/vsizip/path/to/the/file.zip" will work

[VSISStatL\(\)](#) will return the uncompressed size in st_size member and file nature- file or directory - in st_mode member.

Directory listing is available through [VSIReadDir\(\)](#).

Since GDAL 1.8.0, write capabilities are available. They allow creating a new zip file and adding new files to an already existing (or just created) zip file. Read and write operations cannot be interleaved : the new zip must be closed before being re-opened for read.

Additional documentation is to be found at <http://trac.osgeo.org/gdal/wiki/UserDocs/ReadIn-Zip>

Since

GDAL 1.6.0

10.11.2.21 int CPL_DLL VSIsCaseSensitiveFS (const char * pszFilename)

Returns if the filenames of the filesystem are case sensitive.

This method retrieves to which filesystem belongs the passed filename and return TRUE if the filenames of that filesystem are case sensitive.

Currently, this will return FALSE only for Windows real filenames. Other VSI virtual filesystems are case sensitive.

This methods avoid ugly #ifndef WIN32 / #endif code, that is wrong when dealing with virtual filenames.

Parameters

pszFilename	the path of the filesystem object to be tested. UTF-8 encoded.
-------------	--

Returns

TRUE if the filenames of the filesystem are case sensitive.

Since

GDAL 1.8.0

10.11.2.22 void CPL_DLL* VSIMalloc2 (size_t nSize1, size_t nSize2)

VSIMalloc2 allocates (nSize1 * nSize2) bytes. In case of overflow of the multiplication, or if memory allocation fails, a NULL pointer is returned and a CE_Failure error is raised with CPLError(). If nSize1 == 0 || nSize2 == 0, a NULL pointer will also be returned. CPLFree() or VSIFree() can be used to free memory allocated by this function.

10.11.2.23 void CPL_DLL* VSIMalloc3 (size_t nSize1, size_t nSize2, size_t nSize3)

VSIMalloc3 allocates (nSize1 * nSize2 * nSize3) bytes. In case of overflow of the multiplication, or if memory allocation fails, a NULL pointer is returned and a CE_Failure error is raised with CPLError(). If nSize1 == 0 || nSize2

`== 0 || nSize3 == 0`, a NULL pointer will also be returned. CPLFree() or VSIFree() can be used to free memory allocated by this function.

10.11.2.24 int CPL_DLL VSIMkdir (const char * *pszPathname*, long *mode*)

Create a directory.

Create a new directory with the indicated mode. The mode is ignored on some platforms. A reasonable default mode value would be 0666. This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX mkdir() function.

Parameters

<i>pszPathname</i>	the path to the directory to create. UTF-8 encoded.
<i>mode</i>	the permissions mode.

Returns

0 on success or -1 on an error.

10.11.2.25 char CPL_DLL** VSIReadDir (const char * *pszPath*)

Read names in a directory.

This function abstracts access to directory contains. It returns a list of strings containing the names of files, and directories in this directory. The resulting string list becomes the responsibility of the application and should be freed with [CSLDestroy\(\)](#) when no longer needed.

Note that no error is issued via CPLError() if the directory path is invalid, though NULL is returned.

This function used to be known as CPLReadDir(), but the old name is now deprecated.

Parameters

<i>pszPath</i>	the relative, or absolute path of a directory to read. UTF-8 encoded.
----------------	---

Returns

The list of entries in the directory, or NULL if the directory doesn't exist. Filenames are returned in UTF-8 encoding.

10.11.2.26 int CPL_DLL VSIRename (const char * *oldpath*, const char * *newpath*)

Rename a file.

Renames a file object in the file system. It should be possible to rename a file onto a new filesystem, but it is safest if this function is only used to rename files that remain in the same directory.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX rename() function.

Parameters

<i>oldpath</i>	the name of the file to be renamed. UTF-8 encoded.
<i>newpath</i>	the name the file should be given. UTF-8 encoded.

Returns

0 on success or -1 on an error.

10.11.2.27 int CPL_DLL VSIRmdir (const char * *pszDirname*)

Delete a directory.

Deletes a directory object from the file system. On some systems the directory must be empty before it can be deleted.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX rmdir() function.

Parameters

<i>pszDirname</i>	the path of the directory to be deleted. UTF-8 encoded.
-------------------	---

Returns

0 on success or -1 on an error.

10.11.2.28 int CPL_DLL VSIStatExL (const char * *pszFilename*, VSISStatBufL * *psStatBuf*, int *nFlags*)

Get filesystem object info.

Fetches status information about a filesystem object (file, directory, etc). The returned information is placed in the VSISStatBufL structure. For portability only the st_size (size in bytes), and st_mode (file type). This method is similar to VSISStat(), but will work on large files on systems where this requires special calls.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX stat() function, with an extra parameter to specify which information is needed, which offers a potential for speed optimizations on specialized and potentially slow virtual filesystem objects (/vsigzip/, /vsicurl/)

Parameters

<i>pszFilename</i>	the path of the filesystem object to be queried. UTF-8 encoded.
<i>psStatBuf</i>	the structure to load with information.
<i>nFlags</i>	0 to get all information, or VSI_STAT_EXISTS_FLAG, VSI_STAT_NATURE_FLAG or VSI_STAT_SIZE_FLAG, or a combination of those to get partial info.

Returns

0 on success or -1 on an error.

Since

GDAL 1.8.0

10.11.2.29 int CPL_DLL VSIStatL (const char * *pszFilename*, VSISStatBufL * *psStatBuf*)

Get filesystem object info.

Fetches status information about a filesystem object (file, directory, etc). The returned information is placed in the VSISStatBufL structure. For portability only the st_size (size in bytes), and st_mode (file type). This method is similar to VSISStat(), but will work on large files on systems where this requires special calls.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX stat() function.

Parameters

<i>pszFilename</i>	the path of the filesystem object to be queried. UTF-8 encoded.
<i>psStatBuf</i>	the structure to load with information.

Returns

0 on success or -1 on an error.

10.11.2.30 int CPL_DLL VSIUnlink (const char * *pszFilename*)

Delete a file.

Deletes a file object from the file system.

This method goes through the VSIFileHandler virtualization and may work on unusual filesystems such as in memory.

Analog of the POSIX unlink() function.

Parameters

<i>pszFilename</i>	the path of the file to be deleted. UTF-8 encoded.
--------------------	--

Returns

0 on success or -1 on an error.

10.12 sdtsdataset.cpp File Reference

```
#include "sdts_al.h"
#include "gdal_pam.h"
#include "ogr_spatialref.h"
```

Classes

- class [SDTSDataset](#)
- class [SDTSRasterBand](#)

10.12.1 Detailed Description

exclude

Index

~DDFModule
 DDFModule, 61
_CPLAssert
 cpl_error.h, 130
_CPLHashSet, 43
_CPLList, 43
 pData, 43
 psNext, 43
_CPLQuadTree, 44
_QuadTreeNode, 44

AddField
 DDFModule, 62
 DDFRecord, 64
Append
 CPLODBCStatement, 49
AppendEscaped
 CPLODBCStatement, 49
Appendf
 CPLODBCStatement, 49
AssembleRings
 SDTSPolygonReader, 85
 SDTSRawPolygon, 91
AttachToPolygons
 SDTSLineReader, 83

CTX_Attribute
 cpl_minixml.h, 143
CTX_Comment
 cpl_minixml.h, 143
CTX_Element
 cpl_minixml.h, 143
CTX_Literal
 cpl_minixml.h, 143
CTX_Text
 cpl_minixml.h, 143
CPL_LSBINT16PTR
 cpl_port.h, 149
CPL_LSBINT32PTR
 cpl_port.h, 149
CPLAddXMLChild
 cpl_minixml.h, 143
CPLAddXMLSibling
 cpl_minixml.h, 143
CPLAtof
 cpl_conv.h, 110
CPLAtofDelim
 cpl_conv.h, 111
CPLAtofM
 cpl_conv.h, 111

CPLBinaryToHex
 cpl_string.h, 153
CPLAlloc
 cpl_conv.h, 111
CPLCheckForFile
 cpl_conv.h, 112
CPLCleanTrailingSlash
 cpl_conv.h, 112
CPLCleanXMLElementName
 cpl_minixml.h, 143
CPLCloneXMLTree
 cpl_minixml.h, 144
CPLCloseShared
 cpl_conv.h, 113
CPLCorrespondingPaths
 cpl_conv.h, 113
CPLCreateXMLElementAndValue
 cpl_minixml.h, 144
CPLCreateXMLNode
 cpl_minixml.h, 145
CPLDecToPackedDMS
 cpl_conv.h, 113
CPLDestroyXMLNode
 cpl_minixml.h, 145
CPLDumpSharedList
 cpl_conv.h, 113
CPLEmergencyError
 cpl_error.h, 130
CPLEncodingCharSize
 cpl_string.h, 153
CPLErrorContext, 44
CPLErrorReset
 cpl_error.h, 131
CPLEscapeString
 cpl_string.h, 154
CPLExtractRelativePath
 cpl_conv.h, 114
CPLFGets
 cpl_conv.h, 114
CPLForceToASCII
 cpl_string.h, 155
CPLFormCIFilename
 cpl_conv.h, 114
CPLFormFilename
 cpl_conv.h, 115
CPLGenerateTempFilename
 cpl_conv.h, 115
CPLGetBasename
 cpl_conv.h, 115

CPLGetConfigOption
 cpl_conv.h, 116

CPLGetCurrentDir
 cpl_conv.h, 116

CPLGetDirname
 cpl_conv.h, 116

CPLGetErrorHandlerUserData
 cpl_error.h, 131

CPLGetExecPath
 cpl_conv.h, 117

CPLGetExtension
 cpl_conv.h, 117

CPLGetFilename
 cpl_conv.h, 117

CPLGetLastErrorMsg
 cpl_error.h, 131

CPLGetLastErrorMessage
 cpl_error.h, 131

CPLGetLastErrorType
 cpl_error.h, 131

CPLGetPath
 cpl_conv.h, 118

CPLGetSharedList
 cpl_conv.h, 118

CPLGetSymbol
 cpl_conv.h, 118

CPLGetValueType
 cpl_string.h, 155

CPLGetXMLNode
 cpl_minixml.h, 145

CPLGetXMLValue
 cpl_minixml.h, 145

CPLHTTPDestroyResult
 cpl_http.h, 137

CPLHTTPEnabled
 cpl_http.h, 137

CPLHTTPFetch
 cpl_http.h, 137

CPLHTTPParseMultipartMime
 cpl_http.h, 138

CPLHTTPResult, 44

- nDataLen, 44
- nMimeTypeCount, 44
- nStatus, 44
- pabyData, 45
- papszHeaders, 45
- pasMimePart, 45
- pszContentType, 45
- pszErrBuf, 45

CPLHashSetDestroy
 cpl_hash_set.h, 134

CPLHashSetEqualPointer
 cpl_hash_set.h, 134

CPLHashSetEqualStr
 cpl_hash_set.h, 134

CPLHashSetForeach
 cpl_hash_set.h, 134

CPLHashSetHashPointer
 cpl_hash_set.h, 135

 cpl_hash_set.h, 135

CPLHashSetHashStr
 cpl_hash_set.h, 135

CPLHashSetInsert
 cpl_hash_set.h, 135

CPLHashSetLookup
 cpl_hash_set.h, 135

CPLHashSetNew
 cpl_hash_set.h, 136

CPLHashSetRemove
 cpl_hash_set.h, 136

CPLHashSetSize
 cpl_hash_set.h, 136

CPLHexToBinary
 cpl_string.h, 155

CPLIsFilenameRelative
 cpl_conv.h, 119

CPLIsUTF8
 cpl_string.h, 155

CPLKeywordParser, 45

CPLLList
 cpl_list.h, 139

CPLLListAppend
 cpl_list.h, 139

CPLLListCount
 cpl_list.h, 139

CPLLListDestroy
 cpl_list.h, 140

CPLLListGet
 cpl_list.h, 140

CPLLListGetData
 cpl_list.h, 140

CPLLListGetLast
 cpl_list.h, 140

CPLLListGetNext
 cpl_list.h, 140

CPLLListInsert
 cpl_list.h, 141

CPLLListRemove
 cpl_list.h, 141

CPLMalloc
 cpl_conv.h, 119

CPLMimePart, 45

- nDataLen, 46
- pabyData, 46
- papszHeaders, 46

CPLODBCDriverInstaller, 46

- InstallDriver, 46
- RemoveDriver, 47

CPLODBCSession, 47

- EstablishSession, 47
- GetLastError, 48

CPLODBCStatement, 48

- Append, 49
- AppendEscaped, 49
- Appendf, 49
- Clear, 50
- DumpResult, 50

ExecuteSQL, 50
Fetch, 50
GetColCount, 51
GetColData, 51
GetColId, 51
GetColName, 52
GetColNullable, 52
GetColPrecision, 52
GetColSize, 52
GetColType, 53
GetColTypeName, 53
GetColumns, 53
GetPrimaryKeys, 53
GetTables, 54
GetTypeMapping, 54
GetTypeName, 54
CPLOpenShared
 cpl_conv.h, 119
CPLPackedDMSToDec
 cpl_conv.h, 120
CPLParseNameValuePair
 cpl_string.h, 156
CPLParseXMLFile
 cpl_minixml.h, 146
CPLParseXMLString
 cpl_minixml.h, 146
CPLPopErrorHandler
 cpl_error.h, 131
CPLPrintDouble
 cpl_conv.h, 121
CPLPrintInt32
 cpl_conv.h, 121
CPLPrintPointer
 cpl_conv.h, 121
CPLPrintString
 cpl_conv.h, 122
CPLPrintStringFill
 cpl_conv.h, 122
CPLPrintTime
 cpl_conv.h, 122
CPLPrintUIntBig
 cpl_conv.h, 123
CPLProjectRelativeFilename
 cpl_conv.h, 123
CPLPushErrorHandler
 cpl_error.h, 132
CPLPushErrorHandlerEx
 cpl_error.h, 132
CPLQuadTreeCreate
 cpl_quad_tree.h, 150
CPLQuadTreeDestroy
 cpl_quad_tree.h, 151
CPLQuadTreeForeach
 cpl_quad_tree.h, 151
CPLQuadTreeGetAdvisedMaxDepth
 cpl_quad_tree.h, 151
CPLQuadTreeInsert
 cpl_quad_tree.h, 151
CPLQuadTreeSearch
 cpl_quad_tree.h, 151
CPLQuadTreeSetBucketCapacity
 cpl_quad_tree.h, 152
CPLQuadTreeSetMaxDepth
 cpl_quad_tree.h, 152
CPLReadLine
 cpl_conv.h, 123
CPLReadLine2L
 cpl_conv.h, 124
CPLReadLineL
 cpl_conv.h, 124
CPLRealloc
 cpl_conv.h, 124
CPLRecode
 cpl_string.h, 156
CPLRecodeFromWChar
 cpl_string.h, 157
CPLRecodeToWChar
 cpl_string.h, 157
CPLRectObj, 55
CPLRemoveXMLChild
 cpl_minixml.h, 147
CPLResetExtension
 cpl_conv.h, 125
CPLScanDouble
 cpl_conv.h, 125
CPLScanLong
 cpl_conv.h, 125
CPLScanPointer
 cpl_conv.h, 126
CPLScanString
 cpl_conv.h, 126
CPLScanUIntBig
 cpl_conv.h, 126
CPLScanULong
 cpl_conv.h, 127
CPLSearchXMLNode
 cpl_minixml.h, 147
CPLSerializeXMLTree
 cpl_minixml.h, 147
CPLSerializeXMLTreeToFile
 cpl_minixml.h, 147
CPLSetConfigOption
 cpl_conv.h, 127
CPLSetErrorHandler
 cpl_error.h, 132
CPLSetErrorHandlerEx
 cpl_error.h, 133
CPLSetThreadLocalConfigOption
 cpl_conv.h, 127
CPLSetXMLValue
 cpl_minixml.h, 148
CPLSharedFileInfo, 55
CPLStdCallThreadInfo, 55
CPLStrdup
 cpl_conv.h, 127
CPLStripXMLNamespace

cpl_minixml.h, 148
 CPLStrcat
 cpl_string.h, 158
 CPLStrcpy
 cpl_string.h, 158
 CPLStrlwr
 cpl_conv.h, 128
 CPLStrnlen
 cpl_string.h, 159
 CPLStrtod
 cpl_conv.h, 128
 CPLStrtodDelim
 cpl_conv.h, 128
 CPLStrtof
 cpl_conv.h, 129
 CPLStrtofDelim
 cpl_conv.h, 129
 CPLUnescapeString
 cpl_string.h, 159
 CPLUnlinkTree
 cpl_conv.h, 129
 CPLXMLENode, 55
 cpl_minixml.h, 143
 eType, 56
 psChild, 56
 psNext, 56
 pszValue, 56
 CPLXMLENodeType
 cpl_minixml.h, 143
 CSLCount
 cpl_string.h, 159
 CSLDestroy
 cpl_string.h, 160
 CSLDuplicate
 cpl_string.h, 160
 CSLFindName
 cpl_string.h, 160
 CSLFindString
 cpl_string.h, 160
 CSLLoad
 cpl_string.h, 161
 CSLLoad2
 cpl_string.h, 161
 CSLMerge
 cpl_string.h, 161
 CSLPartialFindString
 cpl_string.h, 162
 CSLSetNameValue
 cpl_string.h, 162
 CSLSetNameValueSeparator
 cpl_string.h, 162
 CSLTestBoolean
 cpl_string.h, 163
 CSLTokenizeString2
 cpl_string.h, 163
 Clear
 CPLODBCStatement, 50
 ClearIndex

SDTSIndexedReader, 81
 Clone
 DDFRecord, 64
 CloneOn
 DDFRecord, 65
 Close
 DDFModule, 62
 cpl_minixml.h
 CTX_Attribute, 143
 CTX_Comment, 143
 CTX_Element, 143
 CTX_Literal, 143
 CTX_Text, 143
 cpl_conv.h, 109
 CPLAtof, 110
 CPLAtofDelim, 111
 CPLAtofM, 111
 CPLAlloc, 111
 CPLCheckForFile, 112
 CPLCleanTrailingSlash, 112
 CPLCloseShared, 113
 CPLCorrespondingPaths, 113
 CPLDecToPackedDMS, 113
 CPLDumpSharedList, 113
 CPLExtractRelativePath, 114
 CPLFGets, 114
 CPLFormCIFilename, 114
 CPLFormFilename, 115
 CPLGenerateTempFilename, 115
 CPLGetBasename, 115
 CPLGetConfigOption, 116
 CPLGetCurrentDir, 116
 CPLGetDirname, 116
 CPLGetExecPath, 117
 CPLGetExtension, 117
 CPLGetFilename, 117
 CPLGetPath, 118
 CPLGetSharedList, 118
 CPLGetSymbol, 118
 CPLIsFilenameRelative, 119
 CPLMalloc, 119
 CPLOpenShared, 119
 CPLPackedDMSToDec, 120
 CPLPrintDouble, 121
 CPLPrintInt32, 121
 CPLPrintPointer, 121
 CPLPrintString, 122
 CPLPrintStringFill, 122
 CPLPrintTime, 122
 CPLPrintUIntBig, 123
 CPLProjectRelativeFilename, 123
 CPLReadLine, 123
 CPLReadLine2L, 124
 CPLReadLineL, 124
 CPLRealloc, 124
 CPLResetExtension, 125
 CPLScanDouble, 125
 CPLScanLong, 125

CPLScanPointer, 126
CPLScanString, 126
CPLScanUIntBig, 126
CPLScanULong, 127
CPLSetConfigOption, 127
CPLSetThreadLocalConfigOption, 127
CPLStrdup, 127
CPLStrlwr, 128
CPLStrtod, 128
CPLStrtodDelim, 128
CPLStrtof, 129
CPLStrtofDelim, 129
CPLUnlinkTree, 129
cpl_error.h, 130
 _CPLAssert, 130
 CPLEmergencyError, 130
 CPLErrorReset, 131
 CPLGetErrorHandlerUserData, 131
 CPLGetLastErrorMsg, 131
 CPLGetLastErrorNo, 131
 CPLGetLastErrorType, 131
 CPLPopErrorHandler, 131
 CPLPushErrorHandler, 132
 CPLPushErrorHandlerEx, 132
 CPLSetErrorHandler, 132
 CPLSetErrorHandlerEx, 133
cpl_hash_set.h, 133
 CPLHashSetDestroy, 134
 CPLHashSetEqualPointer, 134
 CPLHashSetEqualStr, 134
 CPLHashSetForeach, 134
 CPLHashSetHashPointer, 135
 CPLHashSetHashStr, 135
 CPLHashSetInsert, 135
 CPLHashSetLookup, 135
 CPLHashSetNew, 136
 CPLHashSetRemove, 136
 CPLHashSetSize, 136
cpl_http.h, 137
 CPLHTTPDestroyResult, 137
 CPLHTTPEnabled, 137
 CPLHTTPFetch, 137
 CPLHTTPParseMultipartMime, 138
cpl_list.h, 138
 CPList, 139
 CPListAppend, 139
 CPListCount, 139
 CPListDestroy, 140
 CPListGet, 140
 CPListGetData, 140
 CPListGetLast, 140
 CPListGetNext, 140
 CPListInsert, 141
 CPListRemove, 141
cpl_minixml.h, 141
 CPLAddXMLChild, 143
 CPLAddXMLSibling, 143
 CPLCleanXMLElementName, 143
 CPLCloneXMLTree, 144
 CPLCreateXMLElementAndValue, 144
 CPLCreateXMLNode, 145
 CPLDestroyXMLNode, 145
 CPLGetXMLNode, 145
 CPLGetXMLValue, 145
 CPLParseXMLFile, 146
 CPLParseXMLString, 146
 CPLRemoveXMLChild, 147
 CPLSearchXMLNode, 147
 CPLSerializeXMLTree, 147
 CPLSerializeXMLTreeToFile, 147
 CPLSetXMLValue, 148
 CPLStripXMLNamespace, 148
 CPLXMLNode, 143
 CPLXMLNodeType, 143
cpl_odb.h, 149
cpl_port.h, 149
 CPL_LSBINT16PTR, 149
 CPL_LSBINT32PTR, 149
cpl_quad_tree.h, 150
 CPLQuadTreeCreate, 150
 CPLQuadTreeDestroy, 151
 CPLQuadTreeForeach, 151
 CPLQuadTreeGetAdvisedMaxDepth, 151
 CPLQuadTreeInsert, 151
 CPLQuadTreeSearch, 151
 CPLQuadTreeSetBucketCapacity, 152
 CPLQuadTreeSetMaxDepth, 152
cpl_string.h, 152
 CPLBinaryToHex, 153
 CPEncodingCharSize, 153
 CPEscapeString, 154
 CPLForceToASCII, 155
 CPLGetValueType, 155
 CPLHexToBinary, 155
 CPLIsUTF8, 155
 CPLParseNameValue, 156
 CPLRecode, 156
 CPLRecodeFromWChar, 157
 CPLRecodeToWChar, 157
 CPLStrlcat, 158
 CPLStrlcpy, 158
 CPLStrnlen, 159
 CPLUnescapeString, 159
 CSLCount, 159
 CSLDestroy, 160
 CSLDuplicate, 160
 CSLFindName, 160
 CSLFindString, 160
 CSLLoad, 161
 CSLLoad2, 161
 CSLMerge, 161
 CSLPartialFindString, 162
 CSLSetNameValue, 162
 CSLSetNameValueSeparator, 162
 CSLTestBoolean, 163
 CSLTokenizeString2, 163

cpl_vsi.h, 164
 VSIFCloseL, 165
 VSIFEofL, 166
 VSIFFlushL, 166
 VSIFOpenL, 167
 VSIFReadL, 167
 VSIFReadMultiRangeL, 167
 VSIFSeekL, 168
 VSIFTellL, 168
 VSIFTruncateL, 169
 VSIFWriteL, 169
 VSIFFileFromMemBuffer, 166
 VSIGetMemFileBuffer, 169
 VSIIInstallGZipFileHandler, 170
 VSIIInstallMemFileHandler, 170
 VSIIInstallSparseFileHandler, 171
 VSIIInstallStdinHandler, 171
 VSIIInstallStdoutHandler, 171
 VSIIInstallSubFileHandler, 172
 VSIIInstallTarFileHandler, 172
 VSIIInstallZipFileHandler, 172
 VSIIIsCaseSensitiveFS, 173
 VSIMalloc2, 173
 VSIMalloc3, 173
 VSIMkdir, 174
 VSIRaddir, 174
 VSIRename, 174
 VSIRmdir, 175
 VSIStatExL, 175
 VSIStatL, 175
 VSILUnlink, 176
 CreateDefaultFieldInstance
 DDFRecord, 65
 ctb, 56
 curfile_info, 57
 DDFBinaryFormat
 DDFSUBfieldDefn, 70
 DDFField, 57
 Dump, 57
 GetData, 57
 GetDataSize, 57
 GetFieldDefn, 57
 GetInstanceData, 58
 GetRepeatCount, 58
 GetSubfieldData, 58
 DDFFieldDefn, 59
 Dump, 59
 FindSubfieldDefn, 59
 GetDefaultValue, 60
 GetDescription, 60
 GetFixedWidth, 60
 GetName, 60
 GetSubfield, 60
 GetSubfieldCount, 60
 IsRepeating, 60
 SetRepeatingFlag, 61
 DDFModule, 61
 ~DDFModule, 61
 AddField, 62
 Close, 62
 DDFModule, 61
 DDFModule, 61
 Dump, 62
 FindFieldDefn, 62
 GetField, 62
 GetFieldCount, 62
 Open, 63
 ReadRecord, 63
 Rewind, 63
 DDFRecord, 63
 AddField, 64
 Clone, 64
 CloneOn, 65
 CreateDefaultFieldInstance, 65
 DeleteField, 65
 Dump, 66
 FindField, 66
 GetData, 66
 GetDataSize, 66
 GetField, 66
 GetFieldCount, 66
 GetFloatSubfield, 66
 GetIntSubfield, 67
 GetModule, 67
 GetStringSubfield, 67
 ResizeField, 68
 SetFieldRaw, 68
 SetFloatSubfield, 68
 SetIntSubfield, 69
 SetStringSubfield, 69
 Write, 69
 DDFSubfieldDefn, 70
 DDFBinaryFormat, 70
 Dump, 71
 DumpData, 71
 ExtractFloatData, 71
 ExtractIntData, 71
 ExtractStringData, 72
 FormatFloatValue, 72
 FormatIntValue, 72
 FormatStringValue, 73
 GetDataLength, 73
 GetDefaultValue, 73
 GetFormat, 73
 GetName, 74
 GetType, 74
 GetWidth, 74
 DefaultCSVFileNameTLS, 74
 DeleteField
 DDFRecord, 65
 dfX
 SDTSRawPoint, 90
 dfY
 SDTSRawPoint, 90
 dfZ
 SDTSRawPoint, 90

Dump
 DDFField, 57
 DDFFieldDefn, 59
 DDFModule, 62
 DDFRecord, 66
 DDFSUBfieldDefn, 71
 SDTSAttrRecord, 79
 SDTSFeature, 80
 SDTSRawLine, 88
 SDTSRawPoint, 89
 SDTSRawPolygon, 91

DumpData
 DDFSUBfieldDefn, 71

DumpResult
 CPLODBCStatement, 50

eType
 CPLXMLNode, 56

errHandler, 74

EstablishSession
 CPLODBCSession, 47

ExecuteSQL
 CPLODBCStatement, 50

ExtractFloatData
 DDFSUBfieldDefn, 71

ExtractIntData
 DDFSUBfieldDefn, 71

ExtractStringData
 DDFSUBfieldDefn, 72

Fetch
 CPLODBCStatement, 50

file_in_zip_read_info_s, 74

FillIndex
 SDTSIndexedReader, 81

FindField
 DDFRecord, 66

FindFieldDefn
 DDFModule, 62

FindFileTLS, 74

FindLayer
 SDTSTransfer, 93

FindSubfieldDefn
 DDFFieldDefn, 59

FormatFloatValue
 DDFSUBfieldDefn, 72

FormatIntValue
 DDFSUBfieldDefn, 72

FormatStringValue
 DDFSUBfieldDefn, 73

GZipSnapshot, 75

GetAttr
 SDTSTransfer, 93

GetBlock
 SDTSRasterReader, 86

GetBlockXSize
 SDTSRasterReader, 86

GetBlockYSize

GetBounds
 SDTSTransfer, 93

GetCATD
 SDTSTransfer, 93

GetColCount
 CPLODBCStatement, 51

GetColData
 CPLODBCStatement, 51

GetColId
 CPLODBCStatement, 51

GetColName
 CPLODBCStatement, 52

GetColNullable
 CPLODBCStatement, 52

GetColPrecision
 CPLODBCStatement, 52

GetColSize
 CPLODBCStatement, 52

GetColType
 CPLODBCStatement, 53

GetColTypeName
 CPLODBCStatement, 53

GetColumns
 CPLODBCStatement, 53

GetData
 DDFField, 57
 DDFRecord, 66

GetDataLength
 DDFSUBfieldDefn, 73

GetDataSize
 DDFField, 57
 DDFRecord, 66

GetDefaultValue
 DDFFieldDefn, 60
 DDFSUBfieldDefn, 73

GetDescription
 DDFFieldDefn, 60

GetEntryFilePath
 SDTS_CATD, 75

GetEntryType
 SDTS_CATD, 76

GetEntryTypeDesc
 SDTS_CATD, 76

GetField
 DDFModule, 62
 DDFRecord, 66

GetFieldCount
 DDFModule, 62
 DDFRecord, 66

GetFieldDefn
 DDFField, 57

GetFixedWidth
 DDFFieldDefn, 60

GetFloatSubfield
 DDFRecord, 66

GetFormat
 DDFSUBfieldDefn, 73

GetIndexedFeatureRef
 SDTSIndexedReader, 81

GetInstanceData
 DDFField, 58

GetIntSubfield
 DDFRecord, 67

GetLastError
 CPLODBCSession, 48

GetLayerCATDEntry
 SDTSTransfer, 94

GetLayerIndexedReader
 SDTSTransfer, 94

GetLayerRasterReader
 SDTSTransfer, 94

GetLayerType
 SDTSTransfer, 95

GetMinMax
 SDTSRasterReader, 86

GetModule
 DDFRecord, 67

GetName
 DDFFieldDefn, 60
 DDFSubfieldDefn, 74

GetNextFeature
 SDTSIndexedReader, 81

GetPrimaryKeys
 CPLODBCStatement, 53

GetRasterType
 SDTSRasterReader, 86

GetRepeatCount
 DDFField, 58

GetStringSubfield
 DDFRecord, 67

GetSubfield
 DDFFieldDefn, 60

GetSubfieldCount
 DDFFieldDefn, 60

GetSubfieldData
 DDFField, 58

GetTables
 CPLODBCStatement, 54

GetTransform
 SDTSRasterReader, 86

GetType
 DDFSubfieldDefn, 74

GetTypeMapping
 CPLODBCStatement, 54

GetTypeName
 CPLODBCStatement, 54

GetWidth
 DDFSubfieldDefn, 74

GetXREF
 SDTSTransfer, 95

GetXSize
 SDTSRasterReader, 87

GetYSize
 SDTSRasterReader, 87

InstallDriver
 CPLODBCDriverInstaller, 46

IsIndexed
 SDTSIndexedReader, 82

IsRepeating
 DDFFieldDefn, 60

IsSecondary
 SDTSArrReader, 78

linkedlist_data_s, 75

linkedlist_datablock_internal_s, 75

nAttributes
 SDTSFeature, 80

nDataLen
 CPLHTTPResult, 44
 CPLMimePart, 46

nMimeTypeCount
 CPLHTTPResult, 44

nRecord
 SDTSModId, 83

nRings
 SDTSRawPolygon, 92

nStatus
 CPLHTTPResult, 44

nVertices
 SDTSRawLine, 88
 SDTSRawPolygon, 92

nZone
 SDTS_XREF, 77

oAreaId
 SDTSRawPoint, 90

oEndNode
 SDTSRawLine, 88

oLeftPoly
 SDTSRawLine, 88

oModId
 SDTSFeature, 80

oRightPoly
 SDTSRawLine, 88

oStartNode
 SDTSRawLine, 88

Open
 DDFModule, 63
 SDTSTransfer, 95

pData
 _CPLList, 43

pabyData
 CPLHTTPResult, 45
 CPLMimePart, 46

padfX
 SDTSRawLine, 88
 SDTSRawPolygon, 92

padfY
 SDTSRawLine, 89
 SDTSRawPolygon, 92

padfZ
 SDTSRawLine, 89

SDTSRawPolygon, 92
panRingStart
SDTSRawPolygon, 92
paoATID
SDTSFeature, 80
papszHeaders
CPLHTTPResult, 45
CPLMimePart, 46
ParseContext, 75
pasMimePart
CPLHTTPResult, 45
poATTR
SDTSArrRecord, 79
poWholeRecord
SDTSArrRecord, 79
psChild
CPLXMLNode, 56
psNext
_CPLList, 43
CPLXMLNode, 56
pszContentType
CPLHTTPResult, 45
pszDatum
SDTS_XREF, 77
pszErrBuf
CPLHTTPResult, 45
pszSystemName
SDTS_XREF, 77
pszValue
CPLXMLNode, 56

ReadRecord
DDFModule, 63
RemoveDriver
CPLODBCDriverInstaller, 47
ResizeField
DDFRecord, 68
Rewind
DDFModule, 63
SDTSIndexedReader, 82

SDTS_CATD, 75
GetEntryFilePath, 75
GetEntryType, 76
GetEntryTypeDesc, 76
SDTS_CATDEntry, 76
SDTS_IREF, 76
SDTS_XREF, 77
nZone, 77
pszDatum, 77
pszSystemName, 77
SDTSArrReader, 77
IsSecondary, 78
SDTSArrRecord, 78
Dump, 79
poATTR, 79
poWholeRecord, 79
SDTSDataset, 79
SDTSFeature, 79

Dump, 80
nAttributes, 80
oModId, 80
paoATID, 80
SDTSIndexedReader, 80
ClearIndex, 81
FillIndex, 81
GetIndexedFeatureRef, 81
GetNextFeature, 81
IsIndexed, 82
Rewind, 82
ScanModuleReferences, 82
SDTSLineReader, 82
AttachToPolygons, 83
SDTSModId, 83
nRecord, 83
szModule, 83
szOBRP, 83
SDTSPointReader, 84
SDTSPolygonReader, 84
AssembleRings, 85
SDTSRasterBand, 85
SDTSRasterReader, 85
GetBlock, 86
GetBlockXSize, 86
GetBlockYSize, 86
GetMinMax, 86
GetRasterType, 86
GetTransform, 86
GetXSize, 87
GetYSize, 87
SDTSRawLine, 87
Dump, 88
nVertices, 88
oEndNode, 88
oLeftPoly, 88
oRightPoly, 88
oStartNode, 88
padfX, 88
padfY, 89
padfZ, 89
SDTSRawPoint, 89
dfX, 90
dfY, 90
dfZ, 90
Dump, 89
oAreald, 90
SDTSRawPolygon, 90
AssembleRings, 91
Dump, 91
nRings, 92
nVertices, 92
padfX, 92
padfY, 92
padfZ, 92
panRingStart, 92
SDTSTransfer, 92
FindLayer, 93

GetAttr, 93
 GetBounds, 93
 GetCATD, 93
 GetLayerCATDEntry, 94
 GetLayerIndexedReader, 94
 GetLayerRasterReader, 94
 GetLayerType, 95
 GetXREF, 95
 Open, 95
 SFRegion, 96
 ScanModuleReferences
 SDTSIndexedReader, 82
 sdtsdataset.cpp, 176
 SetFieldRaw
 DDFRecord, 68
 SetFloatSubfield
 DDFRecord, 68
 SetIntSubfield
 DDFRecord, 69
 SetRepeatingFlag
 DDFFieldDefn, 61
 SetStringSubfield
 DDFRecord, 69
 StackContext, 96
 szModule
 SDTSMoId, 83
 szOBRP
 SDTSMoId, 83

 tm_unz_s, 96
 tm_zip_s, 96

 unz_file_info_internal_s, 96
 unz_file_info_s, 96
 unz_file_pos_s, 96
 unz_global_info_s, 96
 unz_s, 97

 VSIArchiveContent, 97
 VSIArchiveEntry, 97
 VSIArchiveEntryOffset, 97
 VSIArchiveFilesystemHandler, 97
 VSIArchiveReader, 98
 VSIBufferedReaderHandle, 98
 VSICacheChunk, 98
 VSICachedFile, 98
 VSIFCloseL
 cpl_vsi.h, 165
 VSIFEofL
 cpl_vsi.h, 166
 VSIFFlushL
 cpl_vsi.h, 166
 VSIFOpenL
 cpl_vsi.h, 167
 VSIFReadL
 cpl_vsi.h, 167
 VSIFReadMultiRangeL
 cpl_vsi.h, 167
 VSIFSeekL
 cpl_vsi.h, 168
 VSIFTellL
 cpl_vsi.h, 168
 VSIFTruncateL
 cpl_vsi.h, 169
 VSIFWriteL
 cpl_vsi.h, 169
 VSIFFileFromMemBuffer
 cpl_vsi.h, 166
 VSIFFileManager, 99
 VSIFFilesystemHandler, 99
 VSIGZipFilesystemHandler, 99
 VSIGZipHandle, 100
 VSIGZipWriteHandle, 100
 VSIGetMemFileBuffer
 cpl_vsi.h, 169
 VSIIInstallGZipFileHandler
 cpl_vsi.h, 170
 VSIIInstallMemFileHandler
 cpl_vsi.h, 170
 VSIIInstallSparseFileHandler
 cpl_vsi.h, 171
 VSIIInstallStdinHandler
 cpl_vsi.h, 171
 VSIIInstallStdoutHandler
 cpl_vsi.h, 171
 VSIIInstallSubFileHandler
 cpl_vsi.h, 172
 VSIIInstallTarFileHandler
 cpl_vsi.h, 172
 VSIIInstallZipFileHandler
 cpl_vsi.h, 172
 VSIIIsCaseSensitiveFS
 cpl_vsi.h, 173
 VSIMalloc2
 cpl_vsi.h, 173
 VSIMalloc3
 cpl_vsi.h, 173
 VSIMemFile, 100
 VSIMemFilesystemHandler, 100
 VSIMemHandle, 101
 VSIMkdir
 cpl_vsi.h, 174
 VSIReadDir
 cpl_vsi.h, 174
 VSIRename
 cpl_vsi.h, 174
 VSIRmdir
 cpl_vsi.h, 175
 VSISparseFileFilesystemHandler, 101
 VSISparseFileHandle, 101
 VSIStatExL
 cpl_vsi.h, 175
 VSIStatL
 cpl_vsi.h, 175
 VSIStdinFilesystemHandler, 101
 VSIStdinHandle, 102
 VSIStdoutFilesystemHandler, 102

VSISubFileHandle, 102
VSISubRedirectFilesystemHandler, 103
VSISubRedirectHandle, 103
VSISubFileFilesystemHandler, 103
VSISubFileHandle, 103
VSITarEntryFileOffset, 104
VSITarFilesystemHandler, 104
VSITarReader, 104
VSIUnixStdioFilesystemHandler, 105
VSIUnixStdioHandle, 105
VSIUnlink
 cpl_vsi.h, 176
VSVirtualHandle, 105
VSIZipEntryFileOffset, 106
VSIZipFilesystemHandler, 106
VSIZipReader, 107
VSIZipWriteHandle, 107

Write

DDFRecord, 69

zip_fileinfo, 107
zip_internal, 108
zlib_filefunc_def_s, 108